

Paradyn Parallel Performance Tools

Dyninst Programmer's Guide

Release 5.1
March 2007

Computer Science Department
University of Wisconsin
Madison, WI 53706
Email: paradyn@cs.wisc.edu
Web: www.paradyn.org

Computer Science Department
University of Maryland
College Park, MD 20742
Email: bugs@dyninst.org
Web: www.dyninst.org

The logo for Dyninst, featuring the word "Dyn" in a large, bold, blue serif font, and the word "inst" in a smaller, blue, italicized sans-serif font positioned below and to the right of "Dyn".

1.	Introduction.....	3
2.	Abstractions	3
3.	Simple Example	4
4.	Interface	5
4.1	CLASS BPATCH	5
	4.1.1 <i>Callbacks</i>	11
4.2	CLASS BPATCH_PROCESS.....	14
4.3	CLASS BPATCH_THREAD.....	20
4.4	CLASS BPATCH_SOURCEOBJ.....	23
4.5	CLASS BPATCH_FUNCTION.....	24
4.6	CLASS BPATCH_POINT	27
4.7	CLASS BPATCH_IMAGE	29
4.8	CLASS BPATCH_MODULE.....	32
4.9	CLASS BPATCH_SNIPPET	35
4.10	CLASS BPATCH_TYPE.....	40
4.11	CLASS BPATCH_VARIABLEEXPR	41
4.12	CLASS BPATCH_FLOWGRAPH	42
4.13	CLASS BPATCH_EDGE	43
4.14	CLASS BPATCH_LOOPTreeNode	44
4.15	CLASS BPATCH_BASICBLOCK	45
4.16	CLASS BPATCH_BASICBLOCKLOOP	47
4.17	CLASS BPATCH_INSTRUCTION.....	48
4.18	CLASS BPATCH_SOURCEBLOCK.....	49
4.19	CLASS BPATCH_CBLOCK.....	49
4.20	CLASS BPATCH_FRAME.....	49
4.21	CONTAINER CLASSES.....	50
	4.21.1 Class <i>BPatch_Vector</i>	50
	4.21.2 Class <i>BPatch_Set</i>	50
4.22	MEMORY ACCESS CLASSES.....	52
	4.22.1 Class <i>BPatch_memoryAccess</i>	52
	4.22.2 Class <i>BPatch_addrSpec_NP</i>	53
	4.22.3 Class <i>BPatch_countSpec_NP</i>	53
4.23	TYPE SYSTEM.....	54
5.	Using the API.....	56
5.1	OVERVIEW OF MAJOR STEPS	56
5.2	CREATING A MUTATOR PROGRAM.....	56
5.3	SETTING UP THE APPLICATION PROGRAM (MUTATEE)	57
5.4	RUNNING THE MUTATOR	58
5.5	ARCHITECTURAL ISSUES.....	58
	5.5.1 <i>Solaris</i>	59
6.	EXAMPLES	59
6.1	COMPLETE EXAMPLE (RETEE)	59
6.2	INSTRUMENTING MEMORY ACCESS.....	62
	Appendix A - Running the Test Cases.....	64
	Appendix B - Common pitfalls	67
	Appendix C – Building Dyninst	69

Appendix D – Dyninst Performance.....	71
References.....	78

1. INTRODUCTION

The normal cycle of developing a program is to edit source code, compile it, and then execute the resulting binary. However, sometimes this cycle can be too restrictive. We may wish to change the program while it is executing, and not have to re-compile, re-link, or even re-execute the program to change the binary. At first thought, this may seem like a bizarre goal, however there are several practical reasons we may wish to have such a system. For example, if we are measuring the performance of a program and discover a performance problem, it might be necessary to insert additional instrumentation into the program to understand the problem. Another application is performance steering; for large simulations, computational scientists often find it advantageous to be able to make modifications to the code and data while the simulation is executing.

This document describes an Application Program Interface (API) to permit the insertion of code into a running program. The API also permits changing or removing subroutine calls from the application program. Runtime code changes are useful to support a variety of applications including debugging, performance monitoring, and to support composing applications out of existing packages. The goal of this API is to provide a machine independent interface to permit the creation of tools and applications that use runtime code patching. The API and a simple test application are described in [1]. This API is based on the idea of Dynamic Instrumentation described in [3].

The key feature of this interface is that it makes it possible to insert and change instrumentation in a running program.

The goal of this API is to keep the interface small and easy to understand. At the same time it needs to be sufficiently expressive to be useful for a variety of applications. The way we have done this is by providing a simple set of abstractions and a simple way to specify the code to insert into the application¹.

2. ABSTRACTIONS

The API is based on abstractions of a program and its state while in execution. The two primary abstractions are points and snippets. A point is a location in a program where instrumentation can be inserted. A snippet is a representation of a bit of executable code to be inserted into a program at a point. For example, if we wished to record the number of times a procedure was invoked, the point would be the first instruction in the procedure, and the snippets would be a statement to increment a counter. Snippets can include conditionals, function calls, and loops.

¹ To generate more complex code, extra (initially un-called subroutines) can be linked into the application program, and calls to these subroutines can be inserted at runtime via this interface.

The API is designed so that a single instrumentation process can insert snippets into multiple processes executing on a single machine. To support multiple processes, two additional abstractions, processes and images, are included in the API. A *process* refers to one-or-more threads of execution and an address space. *Images* refer to the static representation of a program on disk. Images contain points where code can be modified. Each process is associated with exactly one image. Each process contains at least one *thread*, which represents a thread of execution running in that process.

The API includes a simple type system based on structural equivalence. If mutatee programs have been compiled with debugging symbols and the symbols are in a format that Dyninst understands, type checking is performed on code to be inserted into the mutatee. See Section 4.23 for a complete description of the type system.

3. SIMPLE EXAMPLE

To illustrate the ideas of the API, we present several short examples that demonstrate how the API can be used. The full details of the interface are presented in the next section. To prevent confusion, we refer to the process we are modifying as the application, and the program that uses the API to modify the application as the mutator. A mutator is a separate process that modifies an application process.

A mutator program must create a single instance of the class BPatch. This object is used to access functions and information that are global to the library. It must not be destroyed until the mutator has completely finished using the library. For this example, we will assume that the mutator program has declared a global variable called “bpatch” of class BPatch.

The first thing a mutator needs to do is identify the application process to be modified. If the process is already in execution, this can be done by specifying the executable file name and process id of the application as arguments to create an instance of a process object:

```
appProc = bpatch.processAttach(name, processId);
```

This creates a new instance of the BPatch_process class that refers to the existing process. It had no effect on the state of the process (i.e., running or stopped). If the process has not been started, the mutator specifies the pathname and argument list of a program to execute:

```
appProc = bpatch.processCreate(pathname, argv);
```

Once the application thread has been created, the mutator defines the snippet of code to be inserted and the points where they should be inserted. For example, if we wanted to count the number of times a procedure called InterestingProcedure executes, the mutator might look like this:

```

BPatch_image *appImage;
BPatch_Vector<BPatch_point*> *points;
BPatch_Vector<BPatch_function *> functions;

// Open the program image associated with the thread and return a
// handle to it.
appImage = appProc->getImage();

// find and return the function that we wish to instrument
appImage->findFunction("InterestingProcedure", functions);

// find and return the entry point to the "InterestingProcedure".
points = functions[0]->findPoint(BPatch_entry);

// Create a counter variable (but first get a handle to the correct type).
// by allocating in the application's address space.
BPatch_variableExpr *intCounter =
    appProc->malloc(*appImage->findType("int"));

// Create a code block to increment the integer by one.
//     intCounter = intCounter + 1
//
BPatch_arithExpr addOne(BPatch_assign, *intCounter,
    BPatch_arithExpr(BPatch_plus, *intCounter, BPatch_constExpr(1)));

// insert the snippet of code into the application.
appProc->insertBlock(addOne, *points);

// continue execution
appProc->continueExecution();

// wait for mutatee to finish while allowing Dyninst to handle events
while( !appProc->isTerminated() ){
    bpatch.waitForStatusChange();
}

```

4. INTERFACE

This section describes functions in the API. The API is organized as a collection of C++ classes. The primary classes are `BPatch`, `BPatch_process`, `BPatch_thread`, `BPatch_image`, `BPatch_point`, and `BPatch_snippet`. The API also uses a template class called `BPatch_Vector`. This class is based on the Standard Template Library (STL) vector class.

4.1 Class `BPatch`

The `BPatch` class represents the entire Dyninst library. There can only be one instance of this class at a time. This class is used to perform functions and obtain information not specific to a particular thread or image.

```
BPatch_type *createArray(const char *name, BPatch_type *ptr,
    unsigned int low, unsigned int hi)
```

Create a new array type. The name of the type is `name`, and the type of each element is `ptr`. The index of the first element of the array is `low`, and the last is `high`. The standard rules of type compatibility, described in Section 4.23 are used with arrays created using this function.

```
BPatch_type *createEnum(const char *name, BPatch_Vector<char *>
    elementNames, BPatch_Vector<int> elementIds)
BPatch_type *createEnum(const char *name, BPatch_Vector<char *>
    elementNames)
```

Create a new enumerated type. There are two variations of this function. The first one is used to create an enumerated type where the user specifies the identifier (int) for each element. In the second form, the system specifies the identifiers for each element. In both cases, a vector of character arrays is passed to supply the names of the elements of the enumerated type. In the first form of the function, the number of element in the `elementNames` and `elementIds` vectors must be the same, or the type will not be created and this function will return NULL. The standard rules of type compatibility, described in Section 4.23, are used with enums created using this function.

```
BPatch_type *createScalar(const char *name, int size)
```

Create a new scalar type. The name field is used to specify the name of the type, and the `size` parameter is used to specify the size in bytes of each instance of the type. No additional information about this type is supplied. The type is compatible with other scalars with the same name and size.

```
BPatch_type *createStruct(const char *name, BPatch_Vector<char *>
    fieldNames, BPatch_Vector<BPatch_type *> fieldTypes)
```

Create a new structure type. The name of the structure is specified in the `name` parameter. The `fieldNames` and `fieldTypes` vectors specify fields of the type. These two vectors must have the same number of elements or the function will fail (and return NULL). The standard rules of type compatibility, described in Section 4.23 are used with structures created using this function. The size of the structure is the sum of the size of the elements in the `fieldTypes` vector.

```
BPatch_type *createTypedef(const char *name, BPatch_type *ptr)
```

Create a new type called `name` and having the type `ptr`.

```

BPatch_type *createPointer(const char *name, BPatch_type *ptr)
BPatch_type *createPointer(const char *name, BPatch_type *ptr,
    int size)

```

Create a new type, named `name`, which points to objects of type `ptr`. The first form creates a pointer whose size is equal to `sizeof(void*)` on the target platform where the mutatee is running. In the second form, the size of the pointer is the value passed in the `size` parameter.

```

BPatch_type *createUnion(const char *name, BPatch_Vector<char *>
    fieldNames, BPatch_Vector<BPatch_type *> fieldTypes)

```

Create a new union type. The name of the union is specified in the `name` parameter. The `fieldNames` and `fieldTypes` vectors specify fields of the type. These two vectors must have the same number of elements or the function will fail (and return NULL). The size of the union is the size of the largest element in the `fieldTypes` vector.

```

BPatch_Vector<BPatch_process*> *getProcesses()

```

Returns the list of processes that are currently defined. This list includes threads that were directly created by calling `processCreate/processAttach`, and indirectly by the UNIX `fork` or `Window's CreateProcess` system call. It is up to the user to delete this vector when they are done with it.

```

BPatch_process *processAttach(const char *path, int pid)
BPatch_process *processCreate(const char *path, char *argv[],
    char *envp[] = NULL, int stdin_fd=0, int stdout_fd=1, int
    stderr_fd=2)

```

Each of these functions returns a pointer to a new instance of the `BPatch_process` class. The “`path`” parameter needed by these functions should be the pathname of the executable file containing the process’s code. The `processAttach` function returns a `BPatch_process` associated with an existing process. On Linux platforms the `path` parameter can be NULL since the executable image can be derived from the process `pid`. A process attached to using one of these functions is put into the stopped state. The `processCreate` function creates a new process and returns a new `BPatch_process` associated with it. The new process is put into a stopped state before executing any code.

The `stdin_fd`, `stdout_fd`, and `stderr_fd` parameters are used to set the standard input, output, and error of the child process. The default values of these parameters leave the input, output, and error to be the same as the mutator process. To change these values, an open UNIX file descriptor (see `open(1)`) can be passed.

```
bool pollForStatusChange()
```

This is useful for a mutator that needs to periodically check on the status of its managed threads and does not want to have to check each process individually. It returns `true` if there has been a change in the status of one or more threads that has not yet been reported by either `isStopped` or `isTerminated`.

```
void setDebugParsing (bool state)
```

Turn on or off the parsing of debugger information. By default, the debugger information (produced by the `-g` compiler option) is parsed on those platforms that support it. However, for some applications this information can be quite large. To disable parsing this information, call this method with a value of `false` prior to creating a process.

```
void setTrampRecursive (bool state)
```

Turn on or off trampoline recursion. By default, any snippets invoked while another snippet is active will not be executed. This is the safest behavior, since recursively-calling snippets can cause a program to take up all available system resources and die. For example, adding instrumentation code to the start of `printf`, and then calling `printf` from that snippet will result in infinite recursion.

This protection operates at the granularity of an instrumentation point. When snippets are first inserted at a point, code will be created with recursion protection or not, depending on the current state of flag. Changing the flag is **not** retroactive, and inserting more snippets will not change recursion protection at the point. The recursion protection increases the overhead of instrumentation points, so if there is no way for the snippets to call themselves, then calling this method with the parameter `true` will result in a performance gain. The default value of this flag is `false`.

```
bool isTrampRecursive ()
```

Returns whether trampoline recursion is enabled or disabled. True means that it is enabled

```
void setTypeChecking(bool state)
```

Turn on or off type-checking of snippets. By default type-checking is turned on, and an attempt to create a snippet that contains type conflicts will fail. Any snippet expressions created with type-checking off have the type of their left operand. Turning type-checking off, creating a snippet, and then turning type-checking back on is similar to the type cast operation in the C programming language.

```
bool isTypeChecked()
```

Returns true if type-checking of snippets is enabled, and false otherwise,

```
bool waitForStatusChange ()
```

This function waits until there is a status change to some thread that has not yet been reported by either `isStopped` or `isTerminated`, and then returns true. It is more efficient to call this function than to call `pollForStatusChange` in a loop, because `waitForStatusChange` blocks the mutator process while waiting.

```
void setDelayedParsing (bool)
```

Turn on or off delayed parsing. When on, Dyninst will initially parse only the symbol table information in any new modules loaded by the program, and will postpone more thorough analysis (instrumentation point analysis, variable analysis, and discovery of new functions in stripped binaries). This analysis will automatically occur when the information is necessary.

Users which require small run-time perturbation of a program should not delay parsing; the overhead for analysis may occur at unexpected times if it is triggered by internal Dyninst behavior. Users who desire instrumentation of a small number of functions will benefit from delayed parsing.

```
bool delayedParsingOn ()
```

Returns true if delayed parsing is enabled, and false otherwise.

```
void setMergeTramp (bool)
```

Turn on or off inlined tramps. Setting this value to true will make each base trampoline have all of its mini-trampolines be inlined within it. Using inlined mini-tramps may allow instrumentation to execute faster, but inserting and removing instrumentation may take more time. The default setting for this is true

```
bool isMergeTramp ()
```

This returns the current status of inlined trampolines. A value of true indicates that trampolines are inlined.

```
void setSaveFPR (bool)
```

Turn on or off floating point saves. Setting this value to false means that floating point registers will never be saved, which can lead to large performance improvements. The default value is true. Setting this flag may cause incorrect program behavior if the instrumentation does clobber floating point registers, so it should only be used when the user is positive this will never happen.

```
bool isSaveFPRon ()
```

This returns the current status of the floating point saves. True means we are saving floating points based on the analysis for the given platform.

```
void setBaseTrampDeletion(bool)
```

If true, we delete the base tramp when the last corresponding minitramp is deleted. If false, we leave the base tramp in. The default value is false.

```
bool baseTrampDeletion()
```

Returns true if base trampolines are set to be deleted, false otherwise.

```
void getBPatchVersion(int &major, int &minor, int &subminor)
```

Returns Dyninst's version number. The major version number will be stored in `major`, the minor version number in `minor`, and the subminor version in `subminor`. For example, under Dyninst 5.1.0, this function will return 5 in `major`, 1 in `minor`, and 0 in `subminor`.

```
int getNotificationFD()
```

Returns a file descriptor that is suitable for inclusion in a call to `select`. Dyninst will write data to this file descriptor when it to signal a state change in the process. `BPatch::pollForStatusChange` should then be called so that Dyninst can handle the state change. This is useful for applications where the user does not want to block in `BPatch::waitForStatusChange`. The file descriptor will reset when the user calls `BPatch::pollForStatusChange`.

The following functions are deprecated as of Dyninst 5.0. Please consider using `processCreate`, `processAttach`, and `getProcesses` instead.

DEPRECATED

```
BPatch_thread *attachProcess(const char *path, int pid)
```

```
BPatch_thread *createProcess(const char *path,
    char *argv[], char *envp[] = NULL, int stdin_fd=0,
    int stdout_fd=1, int stderr_fd=2)
```

```
BPatch_Vector<BPatch_thread*> *getThreads()
```

4.1.1 Callbacks

The following functions are intended as a way for API users to be informed when an error or significant event occurs. Each function allows a user to register a handler for an event. The return code for all callback registration functions is the address of the handler that was previously registered (which may be NULL if no handler was previously registered). For backwards compatibility reasons, some callbacks may pass a `BPatch_thread` object when a `BPatch_process` may be more appropriate. A `BPatch_thread` may be converted into a `BPatch_process` using `BPatch_thread::getProcess()`.

```
enum BPatchErrorLevel { BPatchFatal, BPatchSerious, BPatchWarning, BPatchInfo };
```

```
typedef void (*BPatchErrorCallback)(BPatchErrorLevel severity,
    int number, char **params)
```

This is the prototype for the error callback function. The severity field indicates how important the error is (from fatal to information/status). The number is a unique number that identifies this error message. Params are the parameters that describe the detail about an error, e.g., the process id where the error occurred. The number and meaning of params depends on the error. However, for a given error number the number of parameters returned will always be the same.

```
BPatchErrorCallback registerErrorCallback(BPatchErrorCallback
    func)
```

This function registers the error callback function with the `BPatch` class. The return value is the address of the previous error callback function. Dyninst users can change the error callback during program execution (e.g., one error callback before a GUI is initialized, and a different one after).

```
typedef void (*BPatchAsyncThreadEventCallback)(
    BPatch_process *proc, BPatch_thread *thread)
```

This is the prototype for most callback functions associated with events that occur in a thread, such as thread creation and destruction events. The `thread` parameter is the thread that triggered the event, and `proc` is the thread's containing process.

```
bool registerThreadEventCallback(BPatch_asyncEventType type,
    BPatchAsyncThreadEventCallback cb)
```

This function registers a callback to occur whenever the process triggers a new thread event. The type parameter can be either one of `BPatch_threadCreateEvent` or

`BPatch_threadDestroyEvent`. Different callbacks can be registered for different values of `type`.

```
typedef void (*BPatchExecCallback) (BPatch_thread *thr)
```

This is the prototype for the exec callback. The `thr` parameter is a thread in the process that called `exec`. You can use the `BPatch_thread::getProcess` function to get the `BPatch_process` that performed the exec operation.

```
BPatchThreadEventCallback registerExecCallback(
    BPatchExecCallback func) Not implemented on Windows.
```

Registers a function to be called when a thread executes an exec system call. When the function is called, the thread performing the exec will be paused.

```
typedef void (*BPatchForkCallback) (BPatch_thread *parent,
    BPatch_thread *child);
```

This is the prototype for the pre-fork and post-fork callbacks. The `parent` parameter is the parent thread, and the `child` parameter is a `BPatch_thread` in the newly created process. When invoked as a pre-fork callback, the `child` is `NULL`.

```
BPatchForkCallback registerPreForkCallback(
    BPatchForkCallback func) not implemented on Windows
```

Registers a function to be called when a `BPatch_thread` forks a new process. This callback is invoked just before the fork is performed. When the callback is invoked, the thread performing the fork will be stopped.

```
BPatchPostForkCallback registerPostForkCallback(
    BPatchPostForkCallback func) not implemented on Windows
```

Registers a function to be called just after the fork is performed. Both the thread performing the fork and the newly created thread will be paused when the callback is invoked. Unless a post fork callback is registered, the mutator will not be attached to any child processes. Since there is overhead associated with each tracked process, not setting the callback allows the Dyninst library to ignore any child processes. This is particularly useful for instrumenting shell processes that create many (potentially) uninteresting children.

```
typedef enum BPatch_exitType { NoExit, ExitedNormally,
                               ExitedViaSignal };
```

```
typedef void (*BPatchExitCallback) (BPatch_thread *proc,
                                     BPatch_exitType exit_type);
```

This is the prototype for the callback function called when a process exit occurs. The `proc` parameter is the process which exited. The `exit_type` parameter indicates how the process exited, either normally or because of a signal. The functions `BPatch_thread::getExitCode()` and `BPatch_thread::getExitSignal()` can be used to get further information about the process exit.

```
BPatchThreadEventCallback registerExitCallback(
    BPatchExitCallback func)
```

Registers a function to be called when a process terminates. For a normal process exit, the callback will actually be called just before the process exit, when the process is at the entry to the `exit()` function (except for Windows). This allows final actions to be taken on the process before it actually exits. The function `BPatch_thread::isTerminated()` will return true in this context even though the process hasn't yet actually exited. In the case of an exit due to a signal, the process will have already exited. On AIX/Solaris/OSF, the reason why a process exited may not be available if the process was not a child of the Dyninst mutator; the mutator will be notified of the process exiting.

```
typedef void (*BPatchDynLibraryCallback) (Bpatch_thread *thr,
                                           Bpatch_module *mod, bool load);
```

This is the prototype for the dynamic linker callback function. The `thr` field contains the thread that loaded or un-loaded a shared library. The `mod` field contains the module that was loaded or unloaded. The `load` Boolean is true if the library was loaded and false if it was unloaded.

```
BPatchThreadEventCallback registerDynLinkCallback(
    BPatchThreadEventCallback func)
```

Registers a function to be called when an application has loaded or unloaded a dynamic library.

```
typedef void (*BPatchOneTimeCodeCallback) (Bpatch_thread *thr,
                                           void *userData, void *returnValue);
```

This is the prototype for the `oneTimeCode` callback function. The `thr` field contains the thread that executed the `oneTimeCode` (if thread-specific) or an undefined thread in the process (if process-wide). The `userData` field contains the value passed to the `oneTimeCode` call. The `returnValue` field contains the return result of the `oneTimeCode` snippet.

```
BPatchOneTimeCodeCallback registerOneTimeCodeCallback(
    BPatchOneTimeCodeCallback func)
```

Registers a function to be called when an application has completed a oneTimeCode.

4.2 Class BPatch_process

The **BPatch_process** class represents a running process, which includes a one or more threads of execution and an address space.

```
const BPatch_image *getImage()
```

Return a handle to the executable file associated with this BPatch_process object.

```
bool getSourceLines( unsigned long addr, std::vector< std::pair<
    const char *, unsigned int > > & lines )
```

This function returns the line information associated with the mutatee address, `addr`. The vector `lines` contains pairs of filenames and line numbers that are associated with `addr`. In many cases only one filename and line number is associated with an address, but certain compiler optimizations may lead to multiple filenames and lines at an address. This information is only available if the mutatee was compiled with debug information.

This function returns `true` if it was able to find any line information at `addr`, and `false` otherwise.

```
bool getAddressRanges( char * fileName, unsigned int lineNo,
    std::vector< std::pair< unsigned long, unsigned long > > &
    ranges )
```

Given a filename and line number, `fileName` and `lineNo`, this function returns the ranges of mutatee addresses that implement the code range in the output parameter `ranges`. In many cases a source code line will only have one address range implementing it, however compiler optimizations may turn this into multiple, disjoint address ranges. This information is only available if the mutatee was compiled with debug information.

This function returns `true` if it was able to find any line information, `false` otherwise.

```
bool stopExecution()
bool continueExecution()
bool terminateExecution()
```

These three functions change the running state of the process. `stopExecution` puts the process into a stopped state. Depending on the operating system, stopping one process may stop all threads associated with a process. `continueExecution` continues execution of the process. `terminateExecution` terminates execution of the process and will invoke the exit callback if one is registered. Each function returns true on success, or false for failure. Stopping or continuing a terminated thread will fail and these functions will return false.

```
bool isStopped()
int stopSignal()
bool isTerminated()
```

These three functions query the status of a process. `isStopped` returns true if the process is currently stopped. If the process is stopped (as indicated by `isStopped`), then `stopSignal` can be called to find out what signal caused the process to stop. `isTerminated` returns true if the process has exited. Any of these functions may be called multiple times, and calling them will not affect the state of the process.

```
int dumpCore(const char *file, const bool terminate) implemented only on AIX
```

This function causes the process to dump its state to the passed file argument. If the `terminate` flag is true, the process is also terminated. The ability to use this function depends on support from the underlying operating system and may not be implemented on all platforms.

```
int dumpImage(const char *file) not implemented on NT
```

This function causes the process to write the in-memory version of the program to the specified file. **This function is not intended for general use, but rather to help debug implementations of Dyninst. Its semantics and level of implementation vary greatly between platforms.**

```
BPatch_variableExpr *malloc(int n)
BPatch_variableExpr *malloc(const BPatch_type &type)
```

These two functions allocate memory. Memory allocation is from a heap. The heap is not necessarily the same heap used by the application. The available space in the heap may be limited depending on the implementation. The first function, `malloc(int n)`, allocates `n` bytes of memory from the heap. The second function, `malloc(const BPatch_type& t)`, allocates enough memory to hold an object of the specified type. Using the second version is strongly encouraged because it provides additional information to permit better type checking of the passed code. The returned memory is persistent

and will not be released until `BPatch_process::free` is called or the application terminates.

```
void free(const BPatch_variableExpr &ptr)
```

Frees the memory in the passed `ptr`. The programmer is responsible to verify that all code that could reference this memory will not execute again (either by removing all snippets that refer to it, or by analysis of the program).

```
BPatch_variableExpr *getInheritedVariable(const
    BPatch_variableExpr &parentVar)
```

Retrieves a new handle to an existing variable (such as one created by `BPatch_process::malloc`) that was created in a parent process and now exists in a forked child process. When a process forks all existing `BPatch_variableExprs` are copied to the child process, but the Dyninst handles for these objects are not valid in the child `BPatch_process`. This function is invoked on the child process' `BPatch_process`, `parentVar` is a variable from the parent process, and a handle to a variable in the child process is returned. If `parentVar` was not allocated in the parent process, then `NULL` is returned.

```
BPatchSnippetHandle *getInheritedSnippet(BPatchSnippetHandle
    &parentSnippet)
```

This function is similar to `getInheritedVariable`, but operates on `BPatchSnippetHandles`. Given a child process that was created via `fork` and a `BpatchSnippetHandle`, `parentSnippet`, from the parent process, this function will return a handle to `parentSnippet` that is valid in the child process. If it is determined that `parentSnippet` is not associated with the parent process, then `NULL` is returned.

```
BPatchSnippetHandle *insertSnippet(const BPatch_snippet &expr,
    BPatch_point &point,
    BPatch_callWhen when=[BPatch_callBefore| BPatch_callAfter],
    BPatch_snippetOrder order = BPatch_firstSnippet)
BPatchSnippetHandle *insertSnippet(const BPatch_snippet &expr,
    const BPatch_Vector<BPatch_point *> &points,
    BPatch_callWhen when=[BPatch_callBefore| BPatch_callAfter],
    BPatch_snippetOrder order = BPatch_firstSnippet)
```

Inserts a snippet of code at the specified point. If a list of points is supplied, insert the code snippet at each point in the list. The `when` argument specifies when the snippet is to be called; a value of `BPatch_callBefore` indicates that the snippet should be inserted just before the specified point or points in the code, and a value of `BPatch_callAfter` indicates that it should be inserted just after. The `order` argument specifies where the snippet is to be inserted relative to any other snippets previously inserted at the same point. The values `BPatch_firstSnippet` and

`BPatch_lastSnippet` indicate that the snippet should be inserted before or after all snippets, respectively.

It is illegal to use `BPatch_callAfter` with a `BPatch_entry` point. Use `BPatch_callBefore` when instrumenting entry points, which inserts instrumentation before the first instruction in a subroutine. Likewise, it is illegal to use `BPatch_callBefore` with a `BPatch_exit` point. Use `BPatch_callAfter` with exit points, which inserts instrumentation at the last instruction in sub-routine. `insertSnippet` will return `NULL` when used with an illegal pair of points.

```
bool deleteSnippet (BPatchSnippetHandle *handle)
```

Remove the snippet associated with the passed handle. If the handle is not defined for the process, then `deleteSnippet` will return false.

```
bool beginInsertionSet ()
```

Normally, a call to `insertSnippet` immediately injects instrumentation into the mutatee. However, users may wish to insert a set of snippets as a single batch operation. This provides two benefits: First, instrumentation may be inserted in a more efficient manner by `Dyninst`. Second, multiple snippets may be inserted at multiple points as a single operation, with either all snippets being inserted successfully or none. This batch insertion mode is begun with a call to `beginInsertionSet`; after this call, no snippets are actually inserted until a corresponding call to `finalizeInsertionSet`. All calls to `insertSnippet` during batch mode are accumulated internally by `Dyninst`, and the returned `BPatchSnippetHandles` are filled in when `finalizeInsertionSet` is called.

```
bool finalizeInsertionSet (bool atomic)
```

Inserts all snippets accumulated since a call to `beginInsertionSet`. If the atomic parameter is true, then a failure to insert any snippet results in all snippets being removed; effectively, the insertion is all-or-nothing. If the atomic parameter is not set, then snippets are inserted individually. This function also fills in the `BPatchSnippetHandle` structures returned by `insertSnippet`. It returns true on success and false if there was an error inserting any snippets.

```
bool removeFunctionCall (BPatch_point &point)
```

Disables the user function call at the specified location. The point specified must be a valid call point in the image of the requesting process. The purpose of this routine is to permit tools to alter the semantics of a program by eliminating procedure calls. The mechanism to achieve the removal is platform dependent, but might include branching over the call, or replacing it with NOPs. This function only removes a function call; any parameters to the function will still be evaluated.

```
bool replaceCode(BPatch_point *point, BPatch_snippet *snippet)
```

Replaces the instruction identified by `point` with the provided snippet. The provided `point` may represent either a specific instruction (acquired via `BPatch_function::findPoint()`), function entry, function exit, or a call site. If the point corresponds to a function entry, the first instruction in the function will be replaced. If the point corresponds to a function exit, the return instruction at that exit will be replaced. If the point corresponds to a call site, the call instruction will be replaced. If the point corresponds to a control flow edge, replacement will fail and an error will be returned.

This call returns true if the replacement succeeded, or false otherwise. The replacement mechanism uses similar techniques as our instrumentation mechanism, and can fail in the same circumstances.

WARNING: This function is dangerous. Unlike instrumentation, program state is not saved and restored around the new code. The provided snippet may modify registers and memory. This call may have unexpected effects on program execution, resulting in incorrect results or program crashes.

```
bool replaceFunction (BPatch_function &old, BPatch_function &new)
```

Replaces all calls to user function `old` with calls to `new`. This is done by inserting instrumentation (specifically a `BPatch_funcJumpExpr`) into the beginning of function `old` such that a non-returning jump is made to function `new`. Returns true upon success, false otherwise.

```
bool replaceFunctionCall(BPatch_point &point, BPatch_function &newFunc)
```

Changes the function call at the specified point to the function indicated by `newFunc`. The purpose of this routine is to permit runtime steering tools to change the behavior of programs by replacing a call to one procedure by a call to another. Point must be a function call point. If the change was successful, the return value is true, otherwise false will be returned.

WARNING: Care must be used when replacing functions. In particular if the compiler has performed inter-procedural register allocation between the original caller/callee pair, the replacement may not be safe since the replaced function may clobber registers the compiler thought the callee left untouched. Also the signatures of the both the function being replaced and the new function must be compatible.

```
void setMutationsActive(bool)
```

Enable or disable the execution of snippets for the process. This provides a way to temporarily disable all of the dynamic code patches that have been inserted without having to delete them one by one. All allocated memory will remain unchanged while the patches are disabled. When the mutations are not active, the process control functions (i.e., `stopExecution` and `continueExecution`) can still be used. Requests to insert snippets (including `oneTimeCode`) cannot be made while mutations are disabled.

```
void detach(bool cont)
```

Detaches from the process. The process must be stopped to call this function. Instrumentation and other changes to the process will remain active in the detached copy. The `cont` parameter is used to indicate if the process should be continued as a result of detaching.

Linux does not support detaching from a process while leaving it stopped. All processes are continued after detach on Linux.

```
int getPid()
```

Return the system id for the mutatee process. On UNIX based systems this is a PID. On Windows this is HANDLE object for a process.

```
typedef enum BPatch_exitType { NoExit, ExitedNormally,
                               ExitedViaSignal };
```

```
BPatch_exitType terminationStatus()
```

If the process has exited, `terminationStatus` will indicate whether the process exited normally or because of a signal. If the process has not exited, `NoExit` will be returned. On AIX/Solaris, the reason why a process exited will not be available if the process was not a child of the Dyninst mutator; in this case, `ExitedNormally` will be returned in both normal and signal exit cases.

```
int getExitCode()
```

If the process exited in a normal way, `getExitCode` will return the associated exit code. On AIX/Solaris, this code will not be available if the process was not a child of the Dyninst mutator.

```
int getExitSignal()
```

If the process exited because of a received signal, `getExitSignal` will return the associated signal number. On AIX/Solaris, this code will not be available if the process was not a child of the Dyninst mutator.

```
bool loadLibrary(const char *libname, bool reload=false)
```

Loads a dynamically linked library into the process's address space. The `libname` parameter identifies the file name of the library to be loaded, in the standard way that dynamically linked libraries are specified on the operating system on which the API is running. This function returns true if the library was loaded successfully, otherwise it returns false. If `reload` is true, then the library will be reloaded *at startup* by any rewritten binaries produced with a call to `BPatch_process::dumpPatchedImage`.

```
void oneTimeCode(const BPatch_snippet &expr)
```

Causes `snippet` to be executed by the mutatee immediately. If the process is multithreaded, the snippet is run on a thread chosen by `Dyninst`. If the user requires the snippet to be run on a particular thread, use the `BPatch_thread` version of this function instead. The process must be stopped to call this function. The behavior is synchronous; `oneTimeCode` will not return until after the snippet has been run in the application.

```
bool oneTimeCodeAsync(const BPatch_snippet &expr,
                     void *userData = NULL)
```

This function sets up a snippet to be evaluated by the process at the next available opportunity. When the snippet finishes running `Dyninst` will callback any function registered through `BPatch::registerOneTimeCodeCallback`, with `userData` passed as a parameter. This function return true on success and false if it could not post the oneTimeCode.

If the process is multithreaded, the snippet is run on a thread chosen by `Dyninst`. If the user requires the snippet to be run on a particular thread, use the `BPatch_thread` version of this function instead. The behavior is asynchronous; `oneTimeCodeAsync` returns before the snippet is executed.

If the process is running when `oneTimeCodeAsync` is called, `expr` will be run immediately. If the process is stopped, then `expr` will be run when the process is continued.

4.3 Class `BPatch_thread`

The `BPatch_thread` class operates a thread of execution that is running in a process.

```
void getCallStack(BPatch_Vector<BPatch_frame>& stack)
```

This function fills the given vector with current information about the call stack of the thread. Each stack frame is represented by a `BPatch_frame` (see section 4.20 for information about this class).

```
long getTid()
```

This function returns a platform-specific identifier for this thread. This is the identifier that is used by the threading library. For example, on pthread applications this function will return the thread's pthread_t value.

```
long getLWP()
```

This function returns a platform-specific identifier that the operating system uses to identify this thread. For example, on UNIX platforms this returns the LWP id. On Windows this returns a HANDLE object for the thread.

```
long getBPatchID()
```

This function returns a Dyninst-specific identifier for this thread. These ID's apply only to running threads, the BPatch ID of an already terminated thread may be repeated in a new thread.

```
BPatch_function *getInitialFunction()
```

Returns the function that was used by the application to start this thread. For example, on pthread applications this will return the initial function that was passed to pthread_create.

```
unsigned long getStackTopAddr()
```

Returns the base address for this thread's stack.

```
bool isDeadOnArrival()
```

This function returns true if this thread terminated execution before Dyninst was able to attach to it. Since Dyninst performs new thread detection asynchronously it is possible for a thread to be created and destroyed before Dyninst can attach to it. When this happens, a new BPatch_thread is created, but isDeadOnArrival always returns true for this thread. It is illegal to perform any thread-level operations on a DeadOnArrival thread.

```
BPatch_process *getProcess()
```

Returns the BPatch_process that contains this thread.

```
void oneTimeCode(const BPatch_snippet &expr)
```

Causes the snippet to be evaluated by the process immediately. This is similar to the BPatch_process:oneTimeCode function, except that the snippet is guaranteed to run only on this thread. The process must be stopped to call this function. The behavior is syn-

chronous; oneTimeCode will not return until after the snippet has been run in the application.

```
bool oneTimeCodeAsync(const BPatch_snippet &expr,
                     void *userData = NULL)
```

This function sets up a snippet to be evaluated by this thread at the next available opportunity. When the snippet finishes running Dyninst will callback any function registered through `BPatch::registerOneTimeCodeCallback`, with `userData` passed as a parameter. This function returns true if `expr` was posted and false otherwise.

This is similar to the `BPatch_process:oneTimeCodeAsync` function, except that the snippet is guaranteed to run only on this thread. The process must be stopped to call this function. The behavior is asynchronous; `oneTimeCodeAsync` returns before the snippet is executed.

The following `BPatch_thread` functions are deprecated as of Dyninst 5.0. Please consider using the equivalent functions in the `BPatch_process` class.

DEPRECATED

```
bool getLineAndFile(unsigned long addr, unsigned short&
                    lineNo, char* fileName, int length)
```

```
bool stopExecution()
bool continueExecution()
bool terminateExecution()
```

```
bool isStopped()
int stopSignal()
bool isTerminated()
```

DEPRECATED

```
int dumpCore(const char *file, const bool terminate)
int dumpImage(const char *file)
bool dumpPatchedImage(const char* file)
void enableDumpPatchedImage()
```

```
BPatch_variableExpr *malloc(int n)
BPatch_variableExpr *malloc(const BPatch_type &type)
void free(const BPatch_variableExpr &ptr)
```

DEPRECATED

```
BPatch_variableExpr *getInheritedVariable(
    const BPatch_variableExpr &parentVar)
BPatchSnippetHandle*getInheritedSnippet(
    BPatchSnippetHandle &parentSnippet)
bool getSourceLines( unsigned long addr, std::vector<
std::pair< const char *, unsigned int > > & lines )
```

```

DEPRECATED BPatchSnippetHandle *insertSnippet(const BPatch_snippet
        &expr,
        BPatch_point &point,
        BPatch_callWhen when=[BPatch_callBefore|
        BPatch_callAfter],
        BPatch_snippetOrder order = BPatch_firstSnippet)
BPatchSnippetHandle *insertSnippet(const BPatch_snippet
        &expr,
        const BPatch_Vector<BPatch_point *> &points,
        BPatch_callWhen when=[BPatch_callBefore|
        BPatch_callAfter],
        BPatch_snippetOrder order = BPatch_firstSnippet)
bool deleteSnippet(BPatchSnippetHandle *handle)
DEPRECATED bool removeFunctionCall(BPatch_point &point)
DEPRECATED bool replaceFunction (BPatch_function &old,
        BPatch_function &new)
DEPRECATED bool replaceFunctionCall(BPatch_point &point,
        BPatch_function &newFunc)

void setInheritSnippets(bool inherit)
void setMutationsActive(bool)

DEPRECATED BPatch_image *getImage()
DEPRECATED void detach(bool cont)
DEPRECATED int getPid()
DEPRECATED BPatch_exitType terminationStatus()
DEPRECATED int getExitCode()
DEPRECATED int getExitSignal()
DEPRECATED bool loadLibrary(const char *libname, bool reload=false)
DEPRECATED ~BPatch_thread()

```

4.4 Class BPatch_sourceObj

The BPatch_sourceObj class is the C++ super class for the BPatch_function, BPatch_module, and BPatch_image classes. It provides a set of common methods for all three classes. In addition, it can be used to build a “generic” source navigator using the getObjParent and getSourceObj methods to get parents and children of a given level (i.e. the parent of a module is an image, and the children will be the functions).

```
enum BPatchErrorLevel { BPatchFatal, BPatchSerious, BPatchWarning, BPatchInfo };
```

```
enum BPatch_sourceType {
    BPatch_sourceUnknown,
    BPatch_sourceProgram,
    BPatch_sourceModule,
    BPatch_sourceFunction,
    BPatch_sourceOuterLoop,
    BPatch_sourceLoop,
    BPatch_sourceStatement }
BPatch_sourceType getSrcType()
```

Returns the type of the current source object.

```
void getSourceObj(BPatch_Vector<BPatch_sourceObj *> &objs)
```

Returns the children source objects of the current source object. For example, when called on a BPatch_sourceProgram object this will return objects of type BPatch_sourceFunction. When called on a BPatch_sourceFunction object it may return BPatch_sourceOuterLoop and BPatch_sourceStatement objects.

```
BPatch_sourceObj *getObjParent()
```

Returns the parent source object of the current source object. The parent of a BPatch_image is NULL.

```
BPatch_language getLanguage()
```

Return the source language of the current BPatch_sourceObject. For programs that are written in more than one language, BPatch_mixed will be returned. If there is insufficient information to determine the language, BPatch_unknownLanguage will be returned.

4.5 Class BPatch_function

An object of this class represents a function in the application. A BPatch_image object (see description below) can be used to retrieve a BPatch_function object representing a given function.

```
char *getName(char *buffer, int len)
```

Places the name of the function in `buffer`, up to `len` characters. It returns the value of the buffer parameter.

```
char *getMangledName(char *buffer, int len)
```

Places the mangled (internal symbol) name of the function in `buffer`, up to `len` characters. It returns the value of the buffer parameter.

```
char *getTypedName(char *buffer, int len)
```

Places the full function prototype (from debug information) of the function in `buffer`, up to `len` characters. It returns the value of the buffer parameter.

```
bool getNames (BPatch_vector<const char *> &names)
```

Adds all known names of the function to the vector names, including names generated by weak symbols. It returns true if one or more names were added, and false otherwise. The names reside in memory managed by Dyninst.

```
bool getMangledNames (BPatch_vector<const char *> &names)
```

As above, but returns all known mangled (internal symbol) names.

```
bool getTypedNames (BPatch_vector<const char *> &names)
```

As above, but returns all known function prototypes.

```
BPatch_Vector<BPatch_localVar *> *getParams()
```

Returns a vector of BPatch_localVar snippets that refer the parameters of this function. The position in the vector corresponds to the position in the parameter list (starting from zero). The returned local variables can be used to check the types of functions, and be used in snippet expressions.

```
BPatch_type *getReturnType()
```

Returns the type of the return value for this function.

```
BPatch_Vector<BPatch_localVar *> *getVars()
```

Returns a vector of BPatch_localVar that contain the local variables in this function. These BPatch_localVars can be used as parts of snippets in instrumentation. This function requires debug information to be present in the mutatee. If Dyninst was unable to find any local variables this function will return an empty vector. It is up to the user to free the vector returned by this function.

```
bool isInstrumentable()
```

Returns true if the function can be instrumented, and false if it cannot. Various conditions can cause a function to be uninstrumentable. For example, on some platforms functions smaller than some specific number of bytes cannot be instrumented.

```
bool isSharedLib()
```

This function returns true if the function is defined in a shared library.

```
const char *libraryName()
```

Returns the name of the library that contains this function. If the function is not defined in a library, a NULL will be returned.

```
Bpatch_module *getModule()
```

Returns the module that contains this function. Depending on whether the program was compiled for debugging or the symbol table stripped, this information may not be available. This function returns NULL if module information was not found.

```
char *getModuleName(char *name, int maxLen)
```

Copies the name of the module that contains this function into the buffer pointed to by name. Copies at most maxLen characters and returns a pointer to name.

```
enum BPatch_procedureLocation { BPatch_entry, BPatch_exit,
    BPatch_subroutine, BPatch_allLocations }
```

```
const BPatch_Vector<BPatch_point *> *findPoint(const
    BPatch_procedureLocation loc)
```

Returns the BPatch_point or list of BPatch_points associated with the procedure. It is used to select which type of points associated with the procedure will be returned. BPatch_entry and BPatch_exit request respectively the entry and exit points of the subroutine. BPatch_subroutine returns the list of points where the procedure calls other procedures. If the lookup fails to locate any points of the requested type, NULL is returned.

```
enum BPatch_opCode { BPatch_opLoad, BPatch_opStore,
    BPatch_opPrefetch }
```

```
BPatch_Vector<BPatch_point *> *findPoint(const
    BPatch_Set<BPatch_opCode>& ops)
```

Returns the vector of BPatch_points corresponding to the set of machine instruction types described by the argument. This version is used primarily for memory access instrumentation. The BPatch_opCode is an enumeration of instruction types that may be requested: BPatch_opLoad, BPatch_opStore, and BPatch_opPrefetch. Any combination of these may be requested by passing an appropriate argument set containing the desired types. The instrumentation points created by this function have additional memory access information attached to them. This allows such points to be used for memory access specific snippets (e.g. effective address). The memory access information attached is described under Memory Access classes in section 4.22.1.

```
BPatch_localVar *findLocalVar(const char *name)
```

Searches the function's local variable collection for a given name. This returns a pointer to the local variable if a match is found. This function returns NULL if it fails to find any variables.

```
BPatch_Vector<BPatch_variableExpr *> *findVariable(const char *
    name)
```

Returns a set of variables matching name at the scope of this function. If no variables match in the local scope, then the global scope will be searched for matches. This function returns NULL if it fails to find any variables.

```
BPatch_localVar *findLocalParam(const char *name)
```

Searches the function's parameters for a given name. A `BPatch_localVar *` pointer is returned if a match is found, and `NULL` is returned otherwise.

```
void *getBaseAddr()
```

Returns the starting address of the function in the mutatee's address space.

```
unsigned int getSize()
```

Returns the size of the function in bytes.

```
BPatch_flowGraph *getCFG()
```

Returns the control flow graph for the function, or `NULL` if this information is not available. The `BPatch_flowGraph` is described in section 4.12.

DEPRECATED

These functions are deprecated, and may not be present in future versions of Dyninst. Consider using `BPatch_process::getSourceLines` and `BPatch_process::getAddressRanges` instead

```
bool getLineAndFile(int &start, int &end, char *filename,
                    int &max)
```

```
bool getLineToAddr(unsigned short lineNo,
                   BPatch_Vector<unsigned long>& buffer, bool exactMatch
                   = true)
```

4.6 Class `BPatch_point`

An object of this class represents a location in an application's code at which the library can insert instrumentation. A `BPatch_image` object (see section 4.7) is used to retrieve a `BPatch_point` representing a desired point in the application.

```
enum BPatch_procedureLocation { BPatch_entry, BPatch_exit,
                               BPatch_subroutine, BPatch_address }
```

```
BPatch_procedureLocation getPointType()
```

Returns the type of the point.

```
BPatch_function *getCalledFunction()
```

Returns a `BPatch_function` representing the function that is called at the point. If the point is not a function call site or the target of the call cannot be determined, then this function returns `NULL`.

```
BPatch_function *getFunction()
```

Returns a `BPatch_function` representing the function in which this point is contained.

```
void *getAddress()
```

Returns the address of the first instruction at this point.

```
bool usesTrap_NP()
```

Returns true if inserting instrumentation at this point requires using a trap. On the x86 architecture, because instructions are of variable size, the instruction at a point may be too small for the API library to replace it with the normal code sequence used to call instrumentation. Also, when instrumentation is placed at points other than subroutine entry, exit, or call points, traps may be used to ensure the instrumentation fits. In this case, the API replaces the instruction with a single-byte instruction that generates a trap. A trap handler then calls the appropriate instrumentation code. Since this technique is used only on some platforms, on other platforms this function always returns false.

```
const MemoryAccess* getMemoryAccess()
```

Returns the memory access object associated with this point. `MemoryAccess` points are described in section 4.22.1.

```
const BPatch_Vector<BPatchSnippetHandle *> getCurrentSnippets()
const BPatch_Vector<BPatchSnippetHandle *>
    getCurrentSnippets(BPatch_callWhen when)
```

Returns the `BPatchSnippetHandles` for the `BPatch_snippets` that are associated with the point. If argument `when` is `BPatch_callBefore`, then `BPatchSnippetHandles` for snippets installed immediately before this point will be returned. Alternatively, if `when` is `BPatch_callAfter`, then `BPatchSnippetHandles` for snippets installed immediately after this point will be returned.

```
const int* getLiveRegisters(int & size) implemented for AIX and AMD64
```

Returns an array of dimension `size` associated with the live general purpose registers for this point. The array slot is a direct map to the register number. A value of '1' means the register is live, '0' means the register is dead.

```
bool isDynamic()
```

This call returns true if this is a dynamic call site (e.g. a call site where the function call is made via a function pointer).

4.7 Class BPatch_image

This class defines a program image (the executable associated with a process). The only way to get a handle to a BPatch_image is via the BPatch_process member function getImage().

```
const BPatch_point *createInstPointAtAddr (caddr_t address)
```

Returns an instrumentation point at the specified address. This function is designed to permit users who wish to insert instrumentation at an arbitrary place in the code segment. Instruction addresses can be found using the BPatch_instruction object (see section 4.17). On x86 platforms, users should take care to ensure that the requested point is not in the middle of a multi-byte instruction.

```
BPatch_Vector<BPatch_variableExpr *> *getGlobalVariables()
```

Returns a vector of global variables that are defined in this image.

```
BPatch_process *getProcess()
```

Returns the BPatch_process associated with this image.

```
char *getProgramFileName(char *name, unsigned int len)
```

Fills provided buffer name with the program's file name up to len characters. The file-name may include path information.

```
bool getSourceObj(BPatch_Vector<BPatch_sourceObj *> &sources)
```

Fills the parameter vector, sources, with the source objects (see section 4.4) that belong to this image. If there are no source objects, the function returns false. Otherwise, it returns true.

```
const BPatch_Vector<BPatch_function *> *getProcedures(
    bool incUninstrumentable = false)
```

Returns a table of the functions in the image.

If the incUninstrumentable flag is set, the returned table of procedures will include uninstrumentable functions. The default behavior is to omit these functions.

```
const BPatch_Vector<BPatch_module *> *getModules()
```

Returns a vector of the modules in the image.

```
bool getVariables(BPatch_Vector<BPatch_variableExpr *> &vars)
```

Fills the parameter vector, vars, with the global variables defined in this image. If there are no variable, the function returns false. Otherwise, it returns true.

```

BPatch_Vector<BPatch_function*> *findFunction(
    const char *name,
    BPatch_Vector<BPatch_function*> &funcs,
    bool showError = true,
    bool regex_case_sensitive = true,
    bool incUninstrumentable = false,
    bool dont_use_regex = false)

```

Returns a vector of `BPatch_function`'s for the function name defined, or `NULL` if the function does not exist. If `name` contains a POSIX-extended regular expression, and `dont_use_regex` is false, a regex search will be performed on function names and matching `BPatch_functions` returned. If `showError` is true, then `dyninst` will report and error via the `BPatch::registerErrorCallback` if no function is found.

If the `incUninstrumentable` flag is set, the returned table of procedures will include uninstrumentable functions. The default behavior is to omit these functions.

[**NOTE:** if `name` is not found to match any demangled function names in the module, the search is repeated as if `name` is a mangled function name. If this second search succeeds, functions with mangled names matching `name` are returned instead]

```

BPatch_Vector<BPatch_function*> *findFunction(
    BPatch_Vector<BPatch_function*> &funcs,
    BPatchFunctionNameSieve bpsieve,
    void *sieve_data = NULL,
    int showError = 0,
    bool incUninstrumentable = false)

```

Return a vector of `BPatch_functions` according to the generalized user-specified filter function `bpsieve`. This permits users to easily build sets of functions according to their own specific criteria. Internally, for each `BPatch_function` `f` in the image, this method makes a call to `bpsieve(f.getName(), sieve_data)`. The user-specified function `bpsieve` is responsible for taking the name argument and determining if it belongs in the output vector, possibly by using extra user-provided information stored in `sieve_data`. If the name argument matches the desired criteria, `bpsieve` should return `true`. If it does not, `bpsieve` should return `false`.

The function `bpsieve` should be defined in accordance with the typedef:

```
bool (*BPatchFunctionNameSieve) (const char *name, void* sieve_data);
```

If the `incUninstrumentable` flag is set, the returned table of procedures will include uninstrumentable functions. The default behavior is to omit these functions.

```
const BPatch_variableExpr *findVariable(const char *name)
const BPatch_variableExpr *findVariable(const BPatch_point
    &scope,
    const char *name) second form of this method is not implemented on NT.
```

Performs a lookup and returns a handle to the named variable. The first form of the function looks up only variables of global scope, and the second form uses the passed BPatch_point as the scope of the variable. The returned BPatch_variableExpr can be used to create references (uses) of the variable in subsequent snippets. The scoping rules used will be those of the source language. If the image was not compiled with debugging symbols, this function will fail even if the variable is defined in the passed scope.

```
const BPatch_type *findType(const char *name)
```

Performs a lookup and returns a handle to the named type. The handle can be used as an argument to malloc to create new variables of the corresponding type.

```
BPatch_module *findModule(const char *name,
    bool substring_match = false)
```

Returns a module matching name if present in the image. If the match fails, NULL is returned. If substring_match is set, the first moduled that has name as a substring of its name is returned (e.g. to find “libpthread.so.1”, search for “libpthread” with substring_match set to true).

```
const char *getUniqueString() not yet implemented
```

Performs a lookup and returns a unique string for this image. Returns a string that can be compared (via strcmp) to indicate if two images refer to the same underlying object file (i.e., executable or library). The contents of the string is implementation specific and defined to have no semantic meaning.

```
bool getSourceLines( unsigned long addr, std::vector< std::pair<
    const char *, unsigned int > > & lines )
```

Given an address, addr, this function returns a vector of pairs of filenames and line numbers at that address. This function is an alias for BPatch_process::getSourceLines (see section 4.2).

```
bool getAddressRanges( char * fileName, unsigned int lineNo,
    std::vector< std::pair< unsigned long, unsigned long > > &
    ranges )
```

Given a file name and line number, fileName and lineNo, this function returns a list of address ranges that this source line was compiled into. This function is an alias for BPatch_process::getAddressRanges (see section 4.2).

DEPRECATED

```
bool getLineToAddr (const char* fileName, unsigned short
                    lineNo, BPatch_Vector<unsigned long>& buffer, bool
                    exactMatch = true)
```

This function is deprecated. Consider using getAddressRanges() instead.

4.8 Class BPatch_module

An object of this class represents a program module, which is part of a program's executable image. A BPatch_module represents a source file in an executable or a shared library. Dyninst automatically creates a module called DEFAULT_MODULE in each executable to hold any objects that it cannot match to a source file. BPatch_module objects are obtained by calling the BPatch_image member function getModules().

```
BPatch_Vector<BPatch_function*> *findFunction(
    const char *name,
    BPatch_Vector<BPatch_function*> &funcs,
    bool notify_on_failure = true,
    bool regex_case_sensitive = true,
    bool incUninstrumentable = false)
```

Returns a vector of BPatch_function's for the function name defined, or NULL if the function does not exist. If *name* contains a POSIX-extended regular expression, a regex search will be performed on function names, and matching BPatch_functions returned. [**NOTE:** the BPatch_Vector argument *funcs* must be declared fully by the user before calling this function – passing in an uninitialized reference will result in undefined behavior.]

If the incUninstrumentable flag is set, the returned table of procedures will include uninstrumentable functions. The default behavior is to omit these functions.

[**NOTE:** if *name* is not found to match any demangled function names in the module, the search is repeated as if *name* is a mangled function name. If this second search succeeds, functions with mangled names matching *name* are returned instead.]

```
BPatch_function *findFunctionByMangled (
    const char *mangled_name,
    bool incUninstrumentable = false)
```

Return a BPatch_function for the C++-mangled function name defined in the module corresponding to the invoking BPatch_module, or NULL if it does not define the function.

If the `incUninstrumentable` flag is set, the returned table of procedures will include uninstrumentable functions. The default behavior is to omit these functions.

```
size_t getAddressWidth()
```

Returns the size (in bytes) of a pointer in this module. On 32-bit systems this function will return 4, and on 64-bit systems this function will return 8.

```
bool getSourceLines( unsigned long addr, std::vector< std::pair<
const char *, unsigned int > > & lines )
```

This function returns the line information associated with the mutatee address, `addr`. The vector `lines` contains pairs of filenames and line numbers that are associated with `addr`. In many cases only one filename and line number is associated with an address, but certain compiler optimizations may lead to multiple filenames and lines at an address. This information is only available if the mutatee was compiled with debug information.

This function may be more efficient than the `BPatch_process` version of this function. Calling `BPatch_process::getSourceLines` will cause Dyninst to parse line information for all modules in a process. If `BPatch_module::getSourceLines` is called then only the debug information in this module will be parsed.

This function returns `true` if it was able to find any line information at `addr`, and `false` otherwise.

```
bool getAddressRanges( char * fileName, unsigned int lineNo,
std::vector< std::pair< unsigned long, unsigned long > > &
ranges )
```

Given a filename and line number, `fileName` and `lineNo`, this function returns the ranges of mutatee addresses that implement the code range in the output parameter `ranges`. In many cases a source code line will only have one address range implementing it, however compiler optimizations may turn this into multiple, disjoint address ranges. This information is only available if the mutatee was compiled with debug information.

This function may be more efficient than the `BPatch_process` version of this function. Calling `BPatch_process::getAddressRange` will cause Dyninst to parse line information for all modules in a process. If `BPatch_module::getAddressRange` is called then only the debug information in this module will be parsed.

This function returns `true` if it was able to find any line information, `false` otherwise.

```
const BPatch_Vector<BPatch_function *> *getProcedures()
```

Returns a vector of the functions in the module.

```
char *getName(char *buffer, int len)
```

This function copies the name of the module into a buffer, up to len characters. It returns the value of the buffer parameter.

```
char *getFullName(char *buffer, int length)
```

Fills `buffer` with the full path name of a module, up to `length` characters when this information is available.

```
unsigned long getSize()
```

Returns the size of the module. The size is defined as the end of the last function minus the start of the first function.

```
bool getVariables(BPatch_Vector<BPatch_variableExpr *> &vars)
```

Fills the vector, `vars`, with the global variables that are specified in this module. Returns false if no results are found and true, otherwise.

```
void *wgetBaseAddr()
```

Returns the base address of the module. This address is defined as the start of the first function in the module.

```
bool isSharedLib()
```

This function returns true if the module is part of a shared library.

```
const char *getUniqueString()
```

Performs a lookup and returns a unique string for this image. Returns a string that can be compared (via `strcmp`) to indicate if two images refer to the same underlying object file (i.e., executable or library). The contents of the string is implementation specific and defined to have no semantic meaning.

These functions are deprecated. Consider using `getSourceLines` instead.

DEPRECATED

```
bool getLineToAddr (const char* fileName, unsigned short
    lineNo, BPatch_Vector<unsigned long>& buffer, bool
    exactMatch = true)

bool getLineToAddr (unsigned short lineNo,
    BPatch_Vector<unsigned long>& buffer, bool exactMatch
    = true)
```

4.9 Class BPatch_snippet

A snippet is an abstract representation of code to insert into a program. Snippets are defined by creating a new instance of the correct subclass of a snippet. For example, to create a snippet to call a function, create a new instance of the class `BPatch_funcCallExpr`. Creating a snippet does not result in code being inserted into an application. Code is generated when a request is made to insert a snippet at a specific point in a program. Sub-snippets may be shared by different snippets (i.e, a handle to a snippet may be passed as an argument to create two different snippets), but whether the generated code is shared (or replicated) between two snippets is implementation dependent.

```
const BPatch_type *getType()
```

Returns the type of the snippet. The `BPatch_type` system is described in section 4.10.

```
float getCost()
```

Returns an estimate of the number of seconds it would take to execute the snippet. The problems with accurately estimating the cost of executing code are numerous and out of the scope of this document[2]. It is important to realize that the returned cost value is, at best, an estimate.

The rest of the classes are derived classes of the class `BPatch_snippet`.

```
BPatch_arithExpr(BPatch_binOp op, const BPatch_snippet &lOperand,
    const BPatch_snippet &rOperand)
```

Performs the required binary operation. The available binary operators are:

Operator	Description
BPatch_assign	assign the value of rOperand to lOperand
BPatch_plus	add lOperand and rOperand
BPatch_minus	subtract rOperand from lOperand
BPatch_divide	divide rOperand by lOperand
BPatch_times	multiply rOperand by lOperand
BPatch_ref	Array reference of the form lOperand[rOperand]
BPatch_seq	Define a sequence of two expressions (similar to comma in C)

```
BPatch_arithExpr(BPatch_unOp, const BPatch_snippet &operand)
```

Defines a snippet consisting of a unary operator. The unary operators are:

Operator	Description
BPatch_negate	Returns the negation of an integer
BPatch_addr	Returns a pointer to a BPatch_variableExpr
BPatch_deref	Dereferences a pointer

```
BPatch_boolExpr(BPatch_relOp op, const BPatch_snippet &lOperand,
const BPatch_snippet &rOperand)
```

Defines a relational snippet. The available operators are:

Operator	Function
BPatch_lt	Return lOperand < rOperand
BPatch_eq	Return lOperand == rOperand
BPatch_gt	Return lOperand > rOperand
BPatch_le	Return lOperand <= rOperand
BPatch_ne	Return lOperand != rOperand
BPatch_ge	Return lOperand >= rOperand
BPatch_and	Return lOperand && rOperand (Boolean and)
BPatch_or	Return lOperand rOperand (Boolean or)

The type of the returned snippet is boolean, and the operands are type checked.

```
BPatch_breakPointExpr()
```

Defines a snippet that stops a process when executed by it. The stop can be detected using the `isStopped` member function of `BPatch_process`, and the program's execution can be resumed by calling the `continueExecution` member function of `BPatch_process`.

```
BPatch_bytesAccessedExpr ()
```

This expression returns the number of bytes accessed by a memory operation. For most load/store architecture machines it is a constant expression returning the number of bytes for the particular style of load or store. This snippet is only valid at a memory operation instrumentation point.

```

BPatch_constExpr(int value)
BPatch_constExpr(long value)
BPatch_constExpr(const char *value)
BPatch_constExpr(const void *value)

```

Defines a constant snippet of the appropriate type. The *char* * form of the constructor creates a constant string; the null-terminated string beginning at the location pointed to by the parameter is copied into the application's address space, and the `BPatch_constExpr` that is created refers to the location to which the string was copied.

```

BPatch_effectiveAddressesExpr ()

```

Defines an expression that contains the effective address of a memory operation. For a multi-word memory operation (i.e. more than the “natural” operation size of the machine), the effective address is the base address of the operation.

```

BPatch_funcCallExpr(const BPatch_function& func,
const BPatch_Vector<BPatch_snippet*> &args)

```

Defines a call to a function, the passed function must be valid for the current code region. `Args` is a list of arguments to pass to the function; the maximum number of arguments varies by platform and is summarized below. If type checking is enabled, the types of the passed arguments are checked against the function to be called (Availability of type checking depends on the source language of the application and program being compiled for debugging).

Platform	Maximum number of arguments
Alpha	5 arguments
AMD64/EMT-64	6 arguments
IA-32	No limit
IA-64	No limit
POWER	8 arguments
SPARC	5 arguments

```

BPatch_funcJumpExpr (const BPatch_function &func)

```

Defines a snippet that represents a non-returning jump to function `func`. `func` must take the same number and type of arguments as the function in which this snippet is inserted; these arguments will be passed to `func`. `func` must also have the same return type. This snippet can be used to change the implementation of a function, or conditionally change it if the snippet is part of an if-statement.

When `func` returns, control flows as a return from the function in which this snippet is inserted.

```

class BPatch_ifExpr(const BPatch_boolExpr &conditional,
                   const BPatch_snippet &tClause,
                   const BPatch_snippet &fClause)
class BPatch_ifExpr(const BPatch_boolExpr &conditional,
                   const BPatch_snippet &tClause)

```

This constructor creates an if statement. The first argument, `conditional`, should be a Boolean expression that will be evaluated to decide which clause should be executed. The second argument, `tClause`, is the snippet to execute if the conditional evaluates to true. The third argument, `fClause`, is the snippet to execute if the conditional evaluates to false. This third argument is optional. Else-if statements, can be constructed by making the `fClause` of an if statement another if statement.

```
BPatch_insnExpr(BPatch_instruction *insn) implemented on x86-64
```

This constructor creates a snippet that allows the user to mimic the effect of an existing instruction. In effect, the snippet “wraps” the instruction and provides a handle to particular components of instruction behavior. This is currently implemented for memory operations, and provides two override methods: `overrideLoadAddress` and `overrideStoreAddress`. Both methods take a `BPatch_snippet` as an argument. Unlike other snippets, this snippet should be installed via a call to `BPatch_process::replaceCode` (to replace the original instruction). For example:

```

// Assume that access is of type BPatch_memoryAccess, as
// provided by a call to BPatch_point->getMemoryAccess. A
// BPatch_memoryAccess is a child of BPatch_instruction, and
// is a valid source of a BPatch_insnExpr.

BPatch_insnExpr insn(access);

// This example will modify a store by increasing the target
// address by 16.

BPatch_arithExpr newStoreAddr(BPatch_plus,
                              BPatch_effectiveAddressExpr(),
                              BPatch_constExpr(16));

// And now override the original store address

insn.overrideStoreAddress(newStoreAddr)

// We now replace the original instruction with the new one.
// Point is a BPatch_point corresponding to the desired location, and
// process is a BPatch_process.

process.replaceCode(point, insn);

```

```
BPatch_paramExpr(int paramNum)
```

This constructor creates an expression whose value is a parameter being passed to a function. `ParamNum` specifies the number of the parameter to return, starting at 0. Since the contents of parameters may change during subroutine execution, this snippet type is

only valid at points that are entries to subroutines, or when inserted at a call point with the when parameter set to `BPatch_callBefore`.

```
BPatch_retExpr()
```

This snippet results in an expression that evaluates to the return value of a subroutine. This snippet type is only valid at `BPatch_exit` points, or at a call point with the when parameter set to `BPatch_callAfter`.

```
BPatch_sequence(const BPatch_Vector<BPatch_snippet*> &items)
```

Defines a sequence of snippets. The passed snippets will be executed in the order in which they appear in the list.

```
BPatch_threadIndex()
```

This snippet returns an integer expression that contains the thread index of the thread that is executing this snippet. The thread index is the same value that is returned on the mutator side by `BPatch_thread::getBPatchID`.

```
BPatch_tidExpr(const BPatch_process *proc)
```

This snippet results in an integer expression that contains the tid of the thread that is **executing** this snippet. This can be used to record the threadId, or to filter instrumentation so that it only executes for a specific thread.

```
BPatch_nullExpr()
```

Defines a null snippet. This snippet contains no executable statements; however it is a useful place holder for the destination of a goto. For example, using goto and a nullExpr, a while loop can be constructed. For example, to construct the while loop:

```
while (i < 3) {
    i++;
}
```

The following snippets should be created:

```
BPatch_nullExpr loopDone;

// if (i > 3) goto loopDone
// First definition is the boolean expression.
// The second, generates the goto and the if statement
BPatch_boolExpr testFlag(BPatch_gt, *intI, BPatch_constExpr(3));
BPatch_ifExpr test(testFlag, BPatch_gotoExpr(loopDone));

// i++
BPatch_arithExpr addOne(BPatch_assign, *intI,
    BPatch_arithExpr(BPatch_plus, *intI, BPatch_constExpr(1)));

BPatch_Vector<BPatch_snippet *> statements;

statements.push_back(&test);
statements.push_back(&addOne);
```

```
statements.push_back(&loopDone);

BPatch_sequence whileLoop(statements);
```

4.10 Class BPatch_type

The class BPatch_type is used to describe the types of variables, parameters, return values, and functions. Instances of the class can represent language predefined types (e.g. int, float), mutatee defined types (e.g., structures compiled into the mutatee application), or mutator defined types (created using the create* methods of the BPatch class).

```
BPatch_Vector<BPatch_field *> *getComponents()
```

Returns a vector of the types of the fields in a BPatch_struct or BPatch_union. If this method is invoked on a type whose BPatch_dataClass is not BPatch_struct or BPatch_union, NULL is returned.

```
BPatch_Vector<BPatch_cblock *> *getCblocks()
```

Returns the common block classes for the type. The methods of the BPatch_cblock can be used to access information about the member of a common block. Since the same named (or anonymous) common block can be defined with different members in different functions, a given common block may have multiple definitions. The vector returned by this function contains one instance of BPatch_cblock for each unique definition of the common block. If this method is invoked on a type whose BPatch_dataClass is not BPatch_common, a NULL will be returned.

```
BPatch_type *getConstituentType()
```

Returns the type of the base type. For a BPatch_array this is the type of each element, for a BPatch_pointer this is the type of the object the pointer points to. For BPatch_typedef types, this is the original type. For all other types, NULL is returned.

```
enum BPatch_dataClass {
    BPatch_dataScalar,          BPatch_dataEnumerated,
    BPatch_dataTypeClass,      BPatch_dataStructure,
    BPatch_dataUnion,          BPatch_dataArray,
    BPatch_dataPointer,        BPatch_dataReference,
    BPatch_dataFunction,       BPatch_dataTypeAttrib,
    BPatch_dataUnknownType,    BPatch_dataMethod,
    BPatch_dataCommon,         BPatch_dataPrimitive,
    BPatch_dataTypeNumber,     BPatch_dataTypeDefine,
    BPatch_dataNullType };
```

```
BPatch_dataClass getDataClass()
```

Returns one of the above data classes for this type.

```
const char *getLow()
const char *getHigh()
```

Returns the string representation of the upper and lower bound of an array. Calling these two methods on a non-array types produces an undefined result.

```
const char *getName()
```

Return the name of the type.

```
bool isCompatible(const BPatch_type &otype)
```

Returns true if the passed type is type compatible with this type. The rules for type compatibility are given in Section 4.21.2. If the two types are not type compatible, the error reporting callback function will be invoked one or more times with additional information about why the types are not compatible.

4.11 Class BPatch_variableExpr

The **BPatch_variableExpr** class is another class derived from `snippet`. It represents a variable or area of memory in a process's address space. A `BPatch_variableExpr` can be obtained from a `BPatch_process` using the `malloc` member function, or from a `BPatch_image` using the `findVariable` member function. `BPatch_variableExpr` provides two member functions not provided by other types of snippets:

```
bool readValue(void *dst)
void readValue(void *dst, int size)
```

Reads the value of the variable in an application's address space that is represented by this `BPatch_variableExpr`. The `dst` parameter is assumed to point to a buffer large enough to hold a value of the variable's type. If the `size` parameter is supplied, then the number of bytes it specifies will be read. For the first version of this method, if the size of the variable is unknown (i.e., no type information), no data is copied and the method returns false.

```
bool writeValue(void *src)
void writeValue(void *src, int size)
```

Changes the value of the variable in an application's address space that is represented by this `BPatch_variableExpr`. The `src` parameter should point to a value of the variable's type. If the `size` parameter is supplied, then the number of bytes it specifies will be written. For the first version of this method, if the size of the variable is unknown (i.e., no type information), no data is copied and the method returns false.

```
void *getBaseAddr()
```

Returns the base address of the variable. This is designed to let users who wish to access elements of arrays or fields in structures do so. It can also be used to obtain the address of

a variable to pass a point to that variable as a parameter to a procedure call. It is similar to the ampersand (&) operator in C.

```
BPatch_Vector<BPatch_variableExpr *> getComponents()
```

Returns a vector of the components of a struct, or union. Each element of the vector is one field of the composite type, and contains a variable expression for accessing it.

4.12 Class BPatch_flowGraph

The **BPatch_flowGraph** class represents the control flow graph of a function. It provides methods for discovering the basic blocks and loops within the function (using which a caller can navigate the graph). A `BPatch_flowGraph` object can be obtained by calling the `getCFG` method of a `BPatch_function` object.

```
bool containsDynamicCallsites()
```

Returns true if the control flow graph contains any dynamic callsites (e.g, calls through a function pointer).

```
void getAllBasicBlocks(BPatch_Set<BPatch_basicBlock*>&)
```

Fills the given set with pointers to all basic blocks in the control flow graph. `BPatch_basicBlock` is described in section 4.15.

```
void getEntryBasicBlock(BPatch_Vector<BPatch_basicBlock*>&)
```

Fills the given vector with pointers to all basic blocks that are entry points to the function. `BPatch_basicBlock` is described in section 4.15.

```
void getExitBasicBlock(BPatch_Vector<BPatch_basicBlock*>&)
```

Fills the given vector with pointers to all basic blocks that are exit points of the function. `BPatch_basicBlock` is described in section 4.15.

```
void getLoops(BPatch_Vector<BPatch_basicBlockLoop*>&)
```

Fills the given vector with a list of all natural(single entry) loops in the control flow graph.

```
void getOuterLoops(BPatch_Vector<BPatch_basicBlockLoop*>&)
```

Fills the given vector with a list of all natural(single entry) outer loops in the control flow graph.

```
BPatch_loopTreeNode *getLoopTree()
```

Returns the root node of the tree of loops in this flow graph.

```
enum BPatch_procedureLocation { BPatch_locLoopEntry,
    BPatch_locLoopExit, BPatch_locLoopStartIter,
    BPatch_locLoopEndIter }
```

```
BPatch_Vector<BPatch_point*> *findLoopInstPoints(const
    BPatch_procedureLocation loc, BPatch_basicBlockLoop *loop);
```

Finds instrumentation points for the given loop that correspond to the given location: loop entry, loop exit, the start of a loop iteration and the end of a loop iteration. `BPatch_locLoopEntry` and `BPatch_locLoopExit` instrumentation points respectively execute once before the first iteration of a loop and after the last iteration. `BPatch_locLoopStartIter` and `BPatch_locLoopEndIter` respectively execute at the beginning and end of each loop iteration.

[**NOTE:** Dyninst is not always able to generate a correct flowgraph in the presence of indirect jumps. If a function has a case statement or indirect jump instructions, the targets of the jumps are found by searching instruction patterns (peep-hole). The instruction patterns generated are compiler specific and the control flow graph analysis include only the ones we have seen. During the control flow graph generation, if a pattern that is not handled is used for case statement or multi-jump instructions in the function address space, the generated control flow graph may not be complete.]

4.13 Class `BPatch_edge`

The `BPatch_edge` class represents a control flow edge in a `BPatch_flowGraph`.

```
BPatch_point *getPoint()
```

Returns an instrumentation point for this edge. This point can be passed to `BPatch_process::insertSnippet` to instrument the edge.

```
enum    BPatch_edgeType    {    CondJumpTaken,    CondJumpNottaken,
    UncondJump, NonJump }
```

```
BPatch_edgeType getType()
```

Returns a type describing this edge. A `CondJumpTaken` edge is found after a conditional branch, along the edge that is taken when the condition is true. A `CondJumpNot-taken` edge follows the path when the condition is not taken. `UncondJump` is used along an edge that flows out of an uncondition branch that is always taken. `NonJump` is an edge that flows out of a basic block that does not end in a jump, but falls through into the next basic block.

```
BPatch_basicBlock *getSource()
```

Returns the source `BPatch_basicBlock` that this edge flows from.

```
BPatch_basicBlock *getTarget()
```

Returns the target `BPatch_basicBlock` that this edge flows to.

4.14 Class `BPatch_loopTreeNode`

The `BPatch_loopTreeNode` class provides a tree interface to a collection of instances of class `BPatch_basicBlockLoop` contained in a `BPatch_flowGraph`. The structure of the tree follows the nesting relationship of the loops in a function's flow graph. Each `BPatch_loopTreeNode` contains a pointer to a loop (represented by `BPatch_basicBlockLoop`), and a set of sub-loops (represented by other `BPatch_loopTreeNode` objects). The root `BPatch_loopTreeNode` instance has a null loop member since a function may contain multiple outer loops, the outer loops are contained in the root instance's vector of children.

Each instance of `BPatch_loopTreeNode` is given a name which indicates its position in the hierarchy of loops. The name of each root loop takes the form of "loop_x", where x is an integer from 1 to n, where n is the number of outer loops in the function. Each sub-loop has the name of its parent, prepended by a "_y", where y is 1 to m, where m is the number of sub-loops under the outer loop. For example, consider the following C function:

```
void foo() {
    int x, y, z, i;
    for (x=0; x<10; x++) {
        for (y = 0; y<10; y++)
            ...
        for (z = 0; z<10; z++)
            ...
    }
    for (i = 0; i<10; i++) {
        ...
    }
}
```

The `foo` function will have a root `BPatch_loopTreeNode`, containing a `NULL` loop entry and two `BPatch_loopTreeNode` children representing the functions outer loops. These children would have names `loop_1` and `loop_2`, respectively representing the `x` and `i` loops. `loop_2` has no children. `loop_1` has two child `BPatch_loopTreeNode` objects, named `loop_1_1` and `loop_1_2`, respectively representing the `y` and `z` loops.

```
BPatch_basicBlockLoop *loop
```

A node in the tree that represents a single `BPatch_basicBlockLoop` instance.

```
BPatch_Vector<BPatch_loopTreeNode *> children
```

The tree nodes for the loops nested under this loop.

```
const char *name()
```

Return a name for this loop that indicates its position in the hierarchy of loops.

```
bool getCallees(BPatch_Vector<BPatch_function *> &v,
               BPatch_process *p)
```

This function fills the vector `v` with the list of functions that are called by this loop.

```
const char *getCalleeName(unsigned int i)
```

This function return the name of the `i`th function called in the loop's body.

```
unsigned int numCallees()
```

Returns the number of callees contained in this loop's body.

```
BPatch_basicBlockLoop *findLoop(const char *name)
```

Finds the loop object for the given canonical loop name.

4.15 Class `BPatch_basicBlock`

The **`BPatch_basicBlock`** class represents a basic block in the application being instrumented. Objects of this class representing the blocks within a function can be obtained using the `BPatch_flowGraph` object for the function. `BPatch_basicBlock` includes methods for navigating through the control flow graph of the containing function.

```
void getSources(BPatch_Vector<BPatch_basicBlock*>&)
```

Fills the given vector with the list of predecessors for this basic block (i.e, basic blocks that have an outgoing edge in the control flow graph leading to this block).

```
void getTargets (BPatch_Vector<BPatch_basicBlock*>&)
```

Fills the given vector with the list of successors for this basic block (i.e, basic blocks that are the destinations of outgoing edges from this block in the control flow graph).

```
bool dominates (BPatch_basicBlock*)
```

This function returns true if the argument is pre-dominated in the control flow graph by this block, and false if it is not.

```
BPatch_basicBlock* getImmediateDominator()
```

Returns the basic block that immediately pre-dominates this block in the control flow graph.

```
void getImmediateDominates (BPatch_Vector<BPatch_basicBlock*>&)
```

Fills the given vector with a list of pointers to the basic blocks that are immediately dominated by this basic block in the control flow graph.

```
void getAllDominates (BPatch_Set<BPatch_basicBlock*>&)
```

Fills the given vector with a list of pointers to all basic blocks that are dominated by this basic block in the control flow graph.

```
void getSourceBlocks (BPatch_Vector<BPatch_sourceBlock*>&)
```

Fills the given vector with a list of source blocks contributing to this basic block's instruction sequence.

```
int getBlockNumber()
```

Returns the ID number of this basic block. The ID numbers are consecutive from 0 to $n-1$, where n is the number of basic blocks in the flow graph to which this basic block belongs.

```
BPatch_Vector<BPatch_instruction *> getInstructions()
```

Returns a vector of the instructions that are contained within this basic block.

```
void getIncomingEdges (BPatch_Vector<BPatch_edge *> &inc)
```

Fills the list `inc` with all of the control flow edges that point to this basic block.

```
BPatch_Vector<BPatch_point *> findPoint (const
    BPatch_Set<BPatch_opCode> &ops)
```

Finds all points in the basic block that match the given operation.

```
void getOutgoingEdges (BPatch_Vector<BPatch_edge *> &out)
```

Fills the list `out` with all of the control flow edges that leave this basic block.

```
unsigned long getStartAddress()
```

This function returns the starting address of the basic block. The address returned is an absolute address.

```
unsigned long getEndAddress()
```

This function returns the end address of the basic block. The address returned is an absolute address.

```
unsigned long getLastInsnAddress()
```

Returns the address of the last instruction in a basic block.

```
bool isEntryBlock()
```

This function returns true if this basic block is an entry block into a function.

```
bool isExitBlock()
```

This function returns true if this basic block is an exit block of a function.

```
unsigned size()
```

Returns the size of a basic block. The size is defined as the difference between the end address and the start address of the basic block.

4.16 Class BPatch_basicBlockLoop

An object of this class represents a loop in the code of the application being instrumented.

```
bool containsAddress(unsigned long addr)
```

Returns true if `addr` is contained within any of the basic blocks that compose this loop, excluding the block of any of its sub-loops.

```
bool containsAddressInclusive(unsigned long addr)
```

Returns true if `addr` is contained within any of the basic blocks that compose this loop, or in the blocks of any of its sub-loops.

```
BPatch_edge *getBackEdge()
```

Returns a pointer to the back edge that defines this natural loop.

```
void getContainedLoops(BPatch_Vector<BPatch_basicBlockLoop*>&)
```

Fills the given vector with a list of the loops nested within this loop.

```
BPatch_flowGraph *getFlowGraph()
```

Returns a pointer to the control flow graph that contains this loop.

```
BPatch_basicBlock *getLoopHead()
```

Returns a pointer to the basic block that is at the head of this loop.

```
void getOuterLoops (BPatch_Vector<BPatch_basicBlockLoop*>&)
```

Fills the given vector with a list of the outer loops nested within this loop.

```
void getLoopBasicBlocks (BPatch_Vector<BPatch_basicBlock*>&)
```

Fills the given vector with a list of all basic blocks that are part of this loop.

```
void getLoopBasicBlocksExclusive (
    BPatch_Vector<BPatch_basicBlock*>&)
```

Fills the given vector with a list of all basic blocks that are part of this loop but not its sub-loops.

```
BPatch_basicBlock* getLoopHead()
```

Returns the basic block at the head of this loop.

```
bool hasAncestor (BPatch_basicBlockLoop*)
```

Returns true if this loop is nested within the given loop (the given loop is one of its ancestors in the tree of loops).

```
bool hasBlock (BPatch_basicBlock *b)
```

Returns true if this loop or any of its sub-loops contain the basic block b, false otherwise.

```
bool hasBlockExclusive (BPatch_basicBlock *b)
```

Returns true if this loop, excluding its sub-loops, contain the basic block b, false otherwise.

```
BPatch_Set<BPatch_variableExpr*>* getLoopIterators() not yet implemented
```

Returns a set containing the variables used as loop iterators.

4.17 Class BPatch_instruction

A `BPatch_instruction` represents a single machine instruction in the `BPatch_flowGraph`. `BPatch_instructions` can be retrieved with the `BPatch_basicBlock::getInstructions` call.

```
void *getAddress ()
```

This function returns the starting address of this instruction. This function returns an address in the mutatee, not in the mutator.

```
BPatch_point *getInstPoint ()
```

This function returns an `BPatch_point` at this instruction. This point can be passed to `BPatch_process::insertSnippet` to instrument this instruction.

4.18 Class `BPatch_sourceBlock`

An object of this class represents a source code level block. Each source block objects consists of a source file and a set of source lines in that source file. This class is used to fill source line information for each basic block in the control flow graph. For each basic block in the control flow graph there is one or more source block object(s) that correspond to the source files and their lines contributing to the instruction sequence of the basic block.

```
const char* getSourceFile ()
```

Returns a pointer to the name of the source file in which this source block occurs.

```
void getSourceLines (BPatch_Vector<unsigned short>&)
```

Fills the given vector with a list of the lines contained within this source block.

4.19 Class `BPatch_cblock`

This class is used to access information about a common block.

```
BPatch_Vector<BPatch_field *> *getComponents ()
```

Returns a vector containing the individual variables of the common block.

```
BPatch_Vector<BPatch_function *> *getFunctions ()
```

Returns a vector of the functions that can see this common block with the set of fields described in `getComponents`. However, other functions that define this common block with a different set of variables (or sizes of any variable) will not be returned.

4.20 Class `BPatch_frame`

A `BPatch_frame` object represents a stack frame. The `BPatch_thread::getCallStack` member function of `BPatch_thread` returns a vector of `BPatch_frame` objects representing the frames currently on the stack.

```
BPatch_frameType getFrameType()
```

Returns the type of the stack frame. Possible types are:

Frame Type	Meaning
BPatch_frameNormal	A normal stack frame.
BPatch_frameSignal	A frame that represents a signal invocation.
BPatch_frameTrampoline	A frame the represents a call into instrumentation code.

```
void *getFP()
```

Returns the frame pointer for the stack frame.

```
void *getPC()
```

Returns the program counter associated with the stack frame.

```
BPatch_function *findFunction()
```

Returns the function associated with the stack frame.

4.21 Container Classes

4.21.1 Class BPatch_Vector

The **BPatch_Vector** class is a container used to hold other objects used by the API. As of Dyninst 5.0 **BPatch_Vector** is an alias for the C++ STL `std::vector`.

4.21.2 Class BPatch_Set

BPatch_Set is another container class, similar to the set class in the Standard Template Library (STL). It maintains a collection of objects and provides fast lookup. Elements are ordered by a comparison function, which can be user-supplied. This allows for efficiently returning a sorted list of elements, or returning the value of the minimum or maximum element.

```
BPatch_Set()
```

A constructor that creates an empty set with the default comparison function.

```
BPatch_Set(const BPatch_Set<T, Compare>& newBPatch_Set)
```

Copy constructor.

```
int size()
```

Returns the number of elements in the set.

```
bool empty()
```

Returns true if the set is empty, or false if it is not.

```
void insert(const T&)
```

Inserts the given element into the set.

```
void remove(const T&)
```

Removes the given element from the set.

```
bool contains(const T&)
```

Returns true if the argument is a member of the set, otherwise returns false.

```
T* elements(T*)
```

Fills an array with a list of the elements in the set that are sorted in ascending order according to the comparison function. The input argument should point to an array large enough to hold the elements. This function returns its input argument, unless the set is empty, in which case it returns NULL.

```
T minimum()
```

Returns the minimum element in the set, as determined by the comparison function. For an empty set, the result is undefined.

```
T maximum()
```

Returns the maximum element in the set, as determined by the comparison function. For an empty set, the result is undefined.

```
BPatch_Set<T, Compare>& operator= (const BPatch_Set<T, Compare>&)
```

The assignment operator.

```
bool operator== (const BPatch_Set<T, Compare>&)
```

The equality operator. Returns true if both sets consist entirely of elements that are each equal to an element in the other set, or if both sets are empty.

```
bool operator!= (const BPatch_Set<T, Compare>&)
```

The inequality operator. Returns true if either set contains an element not in the other set.

```
BPatch_Set<T, Compare>& operator+= (const T&)
```

Adds the given object to the set.

```
BPatch_Set<T, Compare>& operator|= (const BPatch_Set<T, Compare>&)
```

Set union operator. Assigns the result of the union to the set on the left hand side.

```
BPatch_Set<T, Compare>& operator&= (const BPatch_Set<T, Compare>&)
```

Set intersection operator. Assigns the result of the intersection to the set on the left hand side.

```
BPatch_Set<T, Compare>& operator-= (const BPatch_Set<T, Compare>&)
```

Set difference operator. Assigns the difference of the sets to the set on the left hand side.

```
BPatch_Set<T, Compare> operator| (const BPatch_Set<T, Compare>&)
```

Set union operator.

```
BPatch_Set<T, Compare> operator& (const BPatch_Set<T, Compare>&)
```

Set intersection operator.

```
BPatch_Set<T, Compare> operator- (const BPatch_Set<T, Compare>&)
```

Set difference operator.

4.22 Memory Access Classes

Instrumentation points created through `findPoint(const BPatch_Set<BPatch_opCode>& ops)` get memory access information attached to them. This information is used by the memory access snippets, but is also available to the API user. The classes that encapsulate memory access information are contained in the `BPatch_memoryAccess_NP.h` header.

4.22.1 Class `BPatch_memoryAccess`

This class encapsulates a memory access abstraction. It contains information that describes the memory access type: read, write, read/write, or prefetch. It also contains information that allows the effective address and the number of bytes transferred to be determined.

```
bool isALoad_NP()
```

Returns true if the memory access is a load (memory is read into a register).

```
bool isAStore_NP()
```

Returns true if the memory access is write. Some machine instructions may both load and store (e.g, CAS (compare and swap) on SPARC).

```
bool isAPrefetch_NP()
```

Returns true if memory access is a prefetch (i.e, it has no observable effect on user registers). If this returns true, the instruction is considered neither load nor store. *Prefetches are detected only on SPARC.*

```
short prefetchType_NP ()
```

If the memory access is a prefetch, this method returns a platform specific prefetch type. *On SPARC this returns the prefetch type as encoded in the instruction. See the SPARC Architecture Manual (version 9) for details.*

```
BPatch_addrSpec_NP getStartAddr_NP ()
```

Returns an address specification that allows the effective address of a memory reference to be computed. For example, on the x86 platform a memory access instruction operand may contain a base register, an index register, a scaling value, and a constant base. The `BPatch_addrSpec_NP` describes each of these values.

```
BPatch_countSpec_NP getByteCount_NP ()
```

Returns a specification that describes the number of bytes transferred by the memory access.

4.22.2 Class `BPatch_addrSpec_NP`

This class encapsulates the information required to determine an effective address at runtime. The general representation for an address is a sum of two registers and a constant; this may change in future releases. Some architectures use only certain bits of a register (e.g. bits 25:31 of XER register on the Power chip family); these are represented as pseudo-registers. The numbering scheme for registers and pseudo-registers is implementation dependent and should not be relied upon; it may change in future releases.

```
int getImm()
```

Returns the constant offset. This may be positive or negative.

```
int getReg(unsigned i)
```

Return the register number for the *i*-th register in the sum, where $0 \leq i \leq 2$. Register numbers are positive; a value of -1 means no register.

```
int getScale()
```

Returns any scaling factor used in the memory address computation.

4.22.3 Class `BPatch_countSpec_NP`

This class encapsulates the information required to determine the number of bytes transferred by a memory access. In this release it is an alias for `BPatch_addrSpec`. Do not rely on this implementation; it may change in future releases.

4.23 Type System

The Dyninst type system is based on the notion of structural equivalence. Structural equivalence was selected to allow the system the greatest flexibility in allowing users to write mutators that work with applications compiled both with and without debugging symbols enabled. Using the `create*` methods of the `BPatch` class, a mutator can construct type definitions for existing mutatee structures. This information allows a mutator to read and write complex types even if the application program has been compiled without debugging information. However, if the application has been compiled with debugging information, Dyninst will verify the type compatibility of the operations performed by the mutator.

The rules for type computability are that two types must be of the same storage class (i.e. arrays are only compatible with other arrays) to be type compatible. For each storage class, the following additional requirements must be met for two types to be compatible:

`BPatch_dataScalar`

Scalars are compatible if their names are the same (as defined by `strcmp`) and their sizes are the same.

`BPatch_dataPointer`

Pointers are compatible if the types they point to are compatible.

`BPatch_dataFunc`

Functions are compatible if their return types are compatible, they have same number of parameters, and position by position each element of the parameter list is type compatible.

`BPatch_dataArray`

Arrays are compatible if they have the same number of elements (regardless of their lower and upper bounds) and the base element types are type compatible.

`BPatch_dataEnumerated`

Enumerated types are compatible if they have the same number of elements and the identifiers of the elements are the same.

`BPatch_dataStructure`

`BPatch_dataUnion`

Structures and unions are compatible if they have the same number of constituent parts (fields) and item by item each field is type compatible with the corresponds field of the other type.

In addition, if either of the types is the type `BPatch_unkownType`, then the two types are compatible. Variables in mutatee programs that have not been compiled with debugging symbols (or

in the symbols are in a format that the Dyninst library does not recognize) will be of type BPatch_unkownType.

5. USING THE API

In this section, we describe the steps needed to compile your mutator and mutatee programs and to run them. First we give you an overview of the major steps and then we explain each one in detail.

5.1 Overview of Major Steps

To use Dyninst, you have to:

- (1) *Create a mutator program (Section 5.1)*: You need to create a program that will modify some other program. For an example, see the mutator shown in Section 6.
- (2) *Set up the mutatee (Section 5.3)*: On some platforms, you need to link your application with Dyninst's run time instrumentation library. [**NOTE**: this step is only needed in the current release of the API. Future releases will eliminate this restriction.]
- (3) *Run the mutator (Section 5.4)*: The mutator will either create a new process or attach to an existing one (depending on the whether `createProcess` or `attachProcess` is used).

Sections 5.2 through 5.4 explain these steps in more detail. In addition, Section 5.5 describes issues related to specific hardware and operating systems. In this section, we assume that you have already installed the API distribution and setup the `PLATFORM` and `DYNINST_ROOT` environment variables. The installation of the API is described in the `README` file in the distribution tar file.

5.2 Creating a Mutator Program

The first step in using Dyninst is to create a mutator program. The mutator program specifies the mutatee (either by naming an executable to start or by supplying a process ID for an existing process). In addition, your mutator will include the calls to the API library to modify the mutatee. For the rest of this section, we assume that the mutatee is the sample program given in Section 6. The following fragment of a Makefile shows how to link your mutator program with the Dyninst library on most platforms:

```
retee.o: retee.c
$(CC) -c $(CFLAGS) -I$(DYNINST_ROOT)/core/dyinstAPI/h \
    retee.c

retee: retee.o
$(CC) retee.o -L$(DYNINST_ROOT)/lib/$(PLATFORM) \
    -ldyinstAPI -liberty -o retee
```

On Solaris and Linux, the option “-lelf” must also be added to the link step. On Linux, the option “-ldwarf” must also be added to the link step. On Solaris, the option “-lstdc++” must be added to the link step. On Compaq Tru64 UNIX, the option “-lml” must also be supplied. On AIX, the option `-lbsd` must also be added to the link step. You will also need to make sure that the `LD_LIBRARY_PATH` or `LIBPATH` (AIX) environment variable includes the directory that contains the Dyninst shared library. This is typically `$DYNINST_ROOT/lib/$PLATFORM`.

Some of these libraries, such as `libdwarf` and `libelf`, may not be standard on various platforms. Check the `README` file in `core/dyninstAPI` for more information on where to find these libraries.

Under Windows NT, the mutator also needs to be linked with the `dbghelp` library, which is included in the Microsoft Platform SDK. Below is a fragment from a Makefile for Windows NT:

```
CC = cl

retee.obj: retee.c
    $(CC) -c $(CFLAGS) -I$(DYNINST_ROOT)/core/dyninstAPI/h

retee.exe: retee.obj
    link -out:retee.exe retee.obj \
        $(DYNINST_ROOT)\lib\$(PLATFORM)\libdyninstAPI.lib \
        dbghelp.lib
```

5.3 Setting Up the Application Program (mutatee)

On most platforms, you can instrument unmodified binary (a.out) files. However, there is a base shared library that needs to be available to be loaded into your application (by the mutator), and you may wish to create library of pre-compiled instrumentation routines that your mutator will insert calls to.

On most platforms, any additional code that your mutator might need to call in the mutatee (for example files containing instrumentation functions that were too complex to write directly using the API) must be linked with your application. Simply add these files to the line **<insert any additional modules here>** in Figure 1. On SPARC Solaris, AIX, Linux, and Compaq Tru64 UNIX, you may put such code into a dynamically loaded shared library, which your mutator program can load into the mutatee at runtime using the `loadLibrary` member function of `BPatch_process`.

Additionally, on most platforms we need to use the flags `-g` (to generate debugging) when compiling. The command line switches used to specify these options are different for Visual C++ on Windows NT; see section **Error! Reference source not found.** for information about compiling on Windows NT.

To locate the runtime library that Dyninst needs to load into your program, an additional environment variable must be set. The variable `DYNINSTAPI_RT_LIB` should be set to the full pathname of the run time instrumentation library, which should be:

`$DYNINST_ROOT/$PLATFORM/lib/libdyninstAPI_RT.so.1` (UNIX)

`%DYNINST_ROOT%/i386-unknown-nt4.0/lib/libdyninstAPI_RT.dll` (Windows)

Figure 1 is an example of how you would modify the link command in your Makefile (on one of the UNIX-based platforms) to handle the extra link step required by the current version of the API. If your Makefile contained the link step shown in Figure 1:

(a) You would change it to the version shown in Figure 1.

(b) Note that the additions in Figure 1 are shown in bold.

<pre> OBJECTS = main.o this.o that.o LIBDIR = \$DYNINST_ROOT/lib/\$PLATFORM bubba.pd: \${OBJECTS} \${CC} \${OBJECTS} \ <insert any additional modules here> \ -lm -lcurses -ltermcap -o bubba.pd </pre> <p><i>(b) The Link Command Modified to Run Application. Items in Bold face show the changes (additions)</i></p>
<p>Figure 1: Changing Your Makefile to Link an Application as a Dyninst mutatee. Note: some platforms require a few additional options; see Section 5.5.</p>

5.4 Running the Mutator

At this point, you should be ready to run your application program with your mutator. For example, to start the sample program shown in Section 6:


```
% retee foo <pid>
```

5.5 Architectural Issues

Certain platforms require slight modifications to the procedures discussed above. In this subsection, we describe each of them in turn.

5.5.1 Solaris

When using the Sun C or Fortran compilers, specify the `-xs` option together with `-g`. The `-g` option alone will direct the compiler to place debugging information in the object files (`.o` files), but it will not place the debugging information on the executable (`a.out`) file. Use the `-xs` option so that the compiler will add the debugging information to the `a.out` file. The `-xs` option is not needed when using `gcc`. The following is an example of linking on Solaris.



6. EXAMPLES

This section provides a set of example code to show how the various parts of the API are used together.

6.1 Complete Example (retee)

In this section we show a complete program to demonstrate the use of the API. The example is a program called “re-tee.” It takes three arguments: the pathname of an executable program, the process id of a running instance of the same program, and a file name. It adds code to the running program that copies to the named file all output that the program writes to its standard output file descriptor. In this way it works like “tee,” which passes output along to its own standard out while also saving it in a file. The motivation for the example program is that you run a program, and it starts to print copious lines of output to your screen, and you wish to save that output in a file without having to re-run the program.

Using the API to directly create programs is possible, but somewhat tedious. We anticipate that most users of the API will be tool builders who will create higher level languages for specifying instrumentation (e.g. the MDL language[4]).

```

#include <stdio.h>
#include <fcntl.h>
#include "BPatch.h"
#include "BPatch_Vector.h"
#include "BPatch_thread.h"

```

```

BPatch bpatch;

main(int argc, char *argv[])
{
    int pid;

    if (argc != 4) {
        fprintf(stderr, "Usage: %s prog_filename pid log_filename\n", argv[0]);
        exit(1);
    }

    pid = atoi(argv[2]);

    // Attach to the program
    BPatch_thread *appThread = bpatch.attachProcess(argv[1], pid);

    // Read the program's image and get an associated image object
    BPatch_image *appImage = appThread->getImage();

    BPatch_Vector<BPatch_function*> writeFuncs;

    // Try different variations of write depending on platform
    appImage->findFunction("__write_nocancel", writeFuncs);
    if (writeFuncs.size() == 0)
        appImage->findFunction("_write", writeFuncs);
    if (writeFuncs.size() == 0)
        appImage->findFunction("write", writeFuncs);
    if (writeFuncs.size() == 0)
        appImage->findFunction("__write", writeFuncs);

    if (writeFuncs.size() == 0)
        return -1;

    // Find the entry point to the procedure "write"
    BPatch_Vector<BPatch_point *> *points =
    writeFuncs[0]->findPoint(BPatch_entry);

    if ((*points).size() == 0) {
        fprintf(stderr, "Unable to find entry point to \"write.\\\"\\n");
        exit(1);
    }

    // Generate code that opens the file the first time it is called.

    // The code to be generate is:
    // if (!flagVar) {
    //     fd = open(argv[3], O_WRONLY|O_CREAT, 0666);
    //     flagVar = 1;
    // }
    // (1) Find the open function
    BPatch_Vector<BPatch_function *> openFuncs;
    // Try 64-bit open first
    appImage->findFunction("open64", openFuncs);
    if (openFuncs.size() == 0)
        appImage->findFunction("open", openFuncs);
    if (openFuncs.size() == 0)
        appImage->findFunction("__open", openFuncs);

    if (openFuncs.size() == 0) {
        fprintf(stderr, "Unable to find \"open\\\" function\\n");
    }
}

```

```

    exit(1);
}

// (2) Allocate a vector of snippets for the parameters to open
BPatch_Vector<BPatch_snippet *> openArgs;

// (3) Create a string constant expression from argv[3]
BPatch_constExpr fileName(argv[3]);

// (4) Create two more constant expressions _WRONLY|O_CREAT and 0666
BPatch_constExpr fileFlags(O_WRONLY|O_CREAT);
BPatch_constExpr fileMode(0666);

// (5) Push 3 && 4 onto the list from step 2
openArgs.push_back(&fileName);
openArgs.push_back(&fileFlags);
openArgs.push_back(&fileMode);

// (6) create a procedure call using function found at 1 and
//      parameters from step 5.
BPatch_funcCallExpr openCall(*openFuncs[0], openArgs);
void *openFD = appThread->oneTimeCode(openCall);

// (7) allocate a variable to hold the open file descriptor
BPatch_variableExpr *fdVar =
    appThread->malloc(*appImage->findType("int"));

// (8) create assignment statement of variable from step 7 to return
//      value from step 6.
BPatch_arithExpr openFile(BPatch_assign, *fdVar, openCall);

// (9) Find the integer type, and then allocate a variable
//      of this type to be used as a flag to indicate if the
//      open call was made on a previous call to write.
BPatch_variableExpr *flagVar=
    appThread->malloc(*appImage->findType("int"));

// Declare a snippet vector to hold the list of items
BPatch_Vector<BPatch_snippet *> initStatements;

// (10) flagVar = 1;
BPatch_arithExpr setFlag(BPatch_assign, *flagVar, BPatch_constExpr(1));

// (11) make a sequence of the open and the assignment statements
initStatements.push_back(&openFile);
initStatements.push_back(&setFlag);
BPatch_sequence initSequence(initStatements);

// (12) create expression (flagVar == 1)
BPatch_boolExpr testFlag(BPatch_eq, *flagVar, BPatch_constExpr(0));

// (13) use expression #12 and statement #11 to produce if-statement
BPatch_ifExpr initIfNeeded(testFlag, initSequence);

// Generate the code that copies all writes to file descriptor 1
// to our log file.
// Call write with the same data but for our file descriptor
// The C code we generate is:
//     if (parameter[0] == 1) {

```

```

// write(fd, parameter[1], parameter[2])
// }

// Find the write function call
//BPatch_Vector<BPatch_function *>writeFuncs;
//appImage->findFunction("write", writeFuncs);

// Build up a parameter list with the items:
// 1) The file description of our log file
// 2) First parameter to the original function
// 3) Second parameter to the original function
BPatch_Vector<BPatch_snippet *> writeArgs;
BPatch_paramExpr paramBuf(1);
BPatch_paramExpr paramNbyte(2);
BPatch_constExpr openFD_snippet(openFD);
writeArgs.push_back(&openFD_snippet);
writeArgs.push_back(&paramBuf);
writeArgs.push_back(&paramNbyte);

// Create a function call snippet write(fd, parameter[1], parameter[2])
BPatch_funcCallExpr writeCall(*writeFuncs[0], writeArgs);

// Insert the code into the thread.
appThread->insertSnippet(writeCall, *points);

// continue execution of the mutatee
appThread->continueExecution();

// wait for mutatee to terminate and allow Dyninst to handle events
while (!appThread->isTerminated())
    bpatch.waitForStatusChange();

printf("Done.\n");
}

```

6.2 Instrumenting Memory Access

There are two snippets useful for memory access instrumentation: `BPatch_effectiveAddressExpr` and `BPatch_bytesAccessedExpr`. Both have nullary constructors; the result of the snippet depends on the instrumentation point where the snippet is inserted. `BPatch_effectiveAddressExpr` has type `void*`, while `BPatch_bytesAccessedExpr` has type `int`.

These snippets may be used to instrument a given instrumentation point if and only if the point has memory access information attached to it. In this release the only way to create instrumentation points that have memory access information attached to them is via `BPatch_function.findPoint(const BPatch_Set<BPatch_opCode>&)`. For example, to instrument all the loads and stores in a function named *foo* with a call to another function *bar* that takes one argument (the effective address) one may write:

```

// assuming that thr points to some interesting thread
BPatch_thread* thr = ...;
BPatch_image *img = bpthr->getImage();

// build the set that describes the type of accesses we're looking for
BPatch_Set<BPatch_opCode> axs;

```

```
axs.insert(BPatch_opLoad);
axs.insert(BPatch_opStore);

// scan the function foo and create instrumentation points
BPatch_Vector<BPatch_function*> fooFunctions;
img->findFunction("foo", fooFunctions);
BPatch_Vector<BPatch_point*>* r = fooFunctions[0]->findPoint(axs);

// create the printf function call snippet
BPatch_Vector<BPatch_snippet*> printfArgs;
BPatch_constExpr fmt("Access at: %d.\n");
printfArgs.push_back(&fmt);
BPatch_effectiveAddressExpr eae;
printfArgs.push_back(&eae);
BPatch_function *printfFunc = img->findFunction("printf");
BPatch_funcCallExpr printfCall(*printfFunc, printfArgs);

// insert the snippet at the instrumentation points
thr->insertSnippet(printfCall, *r);
```

APPENDIX A - RUNNING THE TEST CASES

[This collection of tests is deprecated, and is superceded by the tests described in Appendix A. These tests will be removed from Dyninst in a point release after version 5.0]

This section describes how to run the Dyninst test cases. The primary purpose of the test cases is to verify that the API has been installed correctly (and for use in regression testing by the developers of the Dyninst library). The code may also be of use to others since it provides a fairly complete example of how to call most of the API methods. The test suite consists of nine mutator programs (`test[1-9]`) and their associated mutatee programs. The mutatee programs are named `testN.mutatee_COMP` where **N** is the test number and **COMP** is the compiler used to build the mutatee (eg. `cc`, `gcc`, `g++`, `xlC`, etc.).

To compile the tests suite, type `make` in the appropriate platform specific directory under (`../dyninstAPI/tests`). This should produce, depending on the platform, 8 to 24 programs and several shared libraries.

To run one of the tests, simply enter the test program name (e.g., `test1`). This will run the test, and the output should be a series of lines indicating each test number as it completes. In addition, the tests take the following command line arguments:

`-attach`

Runs the mutatee process and has the mutator attach to it rather than using the `createProcess` method. The `-attach` option is only available for `test1` and `test2`.

`-relocate`

Rewrites and relocate instrumented functions in mutatee instead of using the traditional trampoline based approach.

`-mutatee <mutatee name>`

Runs the mutatee named `<mutatee name>` rather than the default mutatee for this test. This is useful to run test cases with versions of the mutatee compiled with a systems native compiler in addition to the GNU compilers. If currently supported, the mutatee for the native compiler is named `testN.mutatee_cc` (see table at the end of this section for a list of platforms).

`-m32`

Runs the 32-bit version of the mutatee test. This flag is only valid on AMD64 platforms. This command line flag changes the shared libraries that are loaded to `libtest?_m32.so`, it also changes the mutatee to `test?.mutatee_gcc_m32`. The order of `-m32` and `-mutatee` is important.

`-run <subtest #> <subtest #> ...`

Only runs the specific sub-tests listed. For example, to run sub-test case 4 of test2 you would enter `test2 -run 4`.

`-skip <subtest #> <subtest #> ...`

Skips the specific sub-tests listed. For example, to skip sub-test case 4 of test2 you would enter `test2 -skip 4`. All other tests are run.

`-V`

Prints out the name of the Dyninst runtime library that will be used to run this test. This is useful to check that the environment is correctly setup to run mutator programs.

`-verbose`

Enables detailed debugging output. This is useful when trying to track down the reason that one (or more) of the test cases failed.

`-v+`

Enables the printing of warning level error messages (`BpatchWarning`) to standard output. This is useful for debugging the test cases.

`-v++`

Enable the printing of information and warning level messages via the error reporting callback function (`BPatchWarning` and `BPatchInfo`). These options are useful for debugging the test cases.

Some platforms do not implement all the test cases due to OS restrictions or missing OS features. If a test is not run on a specific platform, the message “Skipped test #XX” will be displayed. If any of the tests produces a line of the form “**Failed test #XX” there is something wrong with the version of the API or its installation. Each test should still produce a message of the form “Passed test #XXX”, and a message at the end indicating that either all tests were passed, or all requested tests were passed (if the `-run` option is used).

[**NOTE:** test2 produces a few lines that look like error messages since it is testing the error reporting features of the API (e.g. “file not found”). Check for the “All tests passed” message at the end to confirm correct execution.]

The following table summarizes the current status of the various tests cases on different platforms and compilers. For each platform, the entry under the column for a test indicates any tests that are currently being skipped due to missing or unsupported features. The notes refer to other possible problems with the platforms. All platforms are built and tested with the gcc 3.3.3 compiler, with the exception of Windows which relies on the native vendor compiler to build the Dyninst libraries.

Platform Information

PLATFORM	Mutatee Compiler(s)	Abbreviation
alpha-dec-osf5.1	gcc, native	osf5.1
i386-unknown-linux2.4	gcc	lnx2.4
ia64-unknown-linux2.4	gcc	lnx-64
x86_64-unknown-linux2.4	gcc	lnx-x86_64
i386-unknown-nt4.0	native	nt4.0
rs6000-ibm-aix5.1	gcc, native	aix5.1
sparc-sun-solaris2.9 (32 bit)	gcc, native	sol2.9

Skipped Sub-Tests

	aix5.1	lnx2.4	lnx-64	lnx-x86_64	nt4.0	osf5.1	sol2.9
Test 1	22, 35		35		21, 22, 35, 37	31, 33, 35, 37	36
Test 2	9	9	9		6, 7, 9, 10, 13	7, 9, 13	
Test 3							
Test 4					N/A	N/A	
Test 5	1, 2, 4-8, 10, 11	11	6	6, 11	N/A	1, 2, 4-8, 10, 11	6
Test 6	4, 5, 7				N/A	4-8	
Test 7					N/A	N/A	
Test 8	2				N/A	N/A	
Test 9	6		N/A	N/A	N/A	N/A	
Test 10	N/A	N/A	N/A	N/A	N/A	N/A	
Test 12	5, 6	5, 6	2, 5, 6	2, 5, 6	N/A	N/A	5, 6
Test 13					N/A	N/A	
Test 14					N/A	N/A	
Test 15					N/A	N/A	

Notes

Platform	Note
i386-unknown-linux2.4	% Warnings generated: -attach "continue: No such process" test2 "wait returned status of an unknown process" We have tested with RedHat Version 9.0
i386-unknown-nt4.0	% Warnings generated: -attach "process::isRunning_() returning true" @ tests 4-15 not implemented on this platform

APPENDIX B - COMMON PITFALLS

This appendix is designed to point out some common pitfalls that users have reported when using the Dyninst system. Many of these are either due to limitations in the current implementations, or reflect design decisions that may not produce the expected behavior from the system.

Attach followed by detach

If a mutator attaches to a mutatee, and immediately exists, the current behavior is that the mutatee is left suspended. To make sure the application continues, call detach with the appropriate flags.

Attaching to a program that has already been modified by Dyninst

If a mutator attaches to a program that has already been modified by a previous mutator, a warning message will be issued. We are working to fix this problem, but the correct semantics are still being specified. Currently, a message is printed to indicate that this has been attempted, and the attach will fail.

Dyninst is event-driven

Dyninst must sometimes handle events that take place in the mutatee, for instance when a new shared library is loaded, or when the mutatee executes a fork or exec. Dyninst handles events when it checks the status of the mutatee, so to allow this the mutator should periodically call one of the functions `BPatch::pollForStatusChange`, `BPatch::waitForStatusChange`, `BPatch_thread::isStopped`, or `BPatch_thread::isTerminated`.

64-bit binaries (Solaris & AIX)

Dyninst does not support 64-bit binaries on Solaris or AIX.

Missing or out-of-date DbgHelp DLL (Windows)

Dyninst requires an up-to-date DbgHelp library on Windows. See the section on Windows-specific architectural issues for details.

Portland Compiler Group – missing debug symbols

The Portland Group compiler (pgcc) on Linux produces debug symbols that are not read correctly by Dyninst. The binaries produced by the compiler do not contain the source file information necessary for Dyninst to assign the debug symbols to the correct module.

When Building Dyninst from Source

Commonly, required external libraries and headers (such as `libdwarf` or `libelf`) are not found correctly by the compiler. Often, such packages are installed, but outside of the compiler's default search path.

Because of this, we have provided the following extension to our make system. If the file `make.config.local` exists inside the `$DYNINST_ROOT/core` directory, it will automatically be included during the build process.

You can then set the makefile variables `FIRST_INCLUDE` and `FIRST_LIBDIR` inside `make.config.local`. These variables represent the compiler flags used during the compilation and linking phase, respectively. These paths will be searched before any others, insuring that the correct package is used. For example:

```
FIRST_INCLUDE=-I/usr/local/packages/libelf-0.8.5/include  
FIRST_LIBDIR =-L/usr/local/packages/libelf-0.8.5/lib
```

APPENDIX C – BUILDING DYNINST

This appendix describes how to build Dyninst from source code, which can be downloaded from <http://www.paradyn.org> or <http://www.dyninst.org>.

BUILDING ON UNIX

Building Dyninst on UNIX platforms is a four step process that involves: unpacking the Dyninst source, installing any Dyninst dependencies, configuring paths in `make.config.local`, and running the build.

Dyninst's source code is packaged in a tar.gz format. If your Dyninst source tarball is called `srcDist_v5.0.tar.gz`, then you could extract it with the command `gunzip srcDist_v5.0.tar.gz ; tar -xvf srcDist_v5.0.tar`. This will create two directories: `core` and `scripts`.

Dyninst has several dependencies, depending on what platform you are using, which must be installed before Dyninst can be built. Note that for most of these packages Dyninst needs to be able to access the package's include files, which means that development versions are required. If a version number is listed for a packaged, then there are known bugs that may affect Dyninst with earlier versions of the package.

Linux/x86	libdwarf-20060327 libelf
Linux/IA-64	libdwarf-20060327 libunwind-0.98.5 libelf
Linux/x86-64	libdwarf-20060327 libelf
Solaris/Sparc	No external dependencies
AIX/Power	No external dependencies
OSF/Alpha	No external dependencies

At the time of this writing the Linux packages could be found at:

- libdwarf - <http://reality.sgiweb.org/davea/dwarf.html>
- libelf - <http://www.mr511.de/software/english.html>
- libunwind - <http://www.hpl.hp.com/research/linux/libunwind/download.php4>

Once the dependencies for Dyninst have been installed, Dyninst must be configured to know where to find these packages. This is done through Dyninst's `core/make.config.local` file. This file must be written in GNU Makefile syntax and must specify directory locations for each dependency. Specifically, `LIBDWARFDIR`, `LIBELFDIR` and `TCLTK_DIR` variables must be set. `LIBDWARFDIR` should be set to the absolute path of libdwarf library where `dwarf.h`

and `libdwarf.h` files reside. `LIBELFDIR` should be set to the absolute path where `libelf.a` and `libelf.so` files are located. Finally, `TCLTK_DIR` variable should be set to the base directory where Tcl is installed.

The next thing is to set `DYNINST_ROOT`, `PLATFORM`, and `LD_LIBRARY_PATH` environment variables. `DYNINST_ROOT` should be set to path of the directory that contains `core` and `scripts` subdirectories.

`PLATFORM` should be set to one of the following values depending upon what operating system you are running on:

<code>alpha-dec-osf5.1</code>	Tru64 UNIX on the Alpha processor
<code>i386-unknown-linux2.4</code>	Linux 2.4/2.6 on an Intel x86 processor
<code>ia64-unknown-linux2.4</code>	Linux 2.4/2.6 on an IA-64 processor
<code>rs6000-ibm-aix5.1</code>	AIX Version 5.1
<code>sparc-sun-solaris2.9</code>	Solaris 2.9 on a SPARC processor
<code>x86_64-unknown-linux2.4</code>	Linux 2.4/2.6 on an AMD-64 processor

`LD_LIBRARY_PATH` variable should be set in a way that it includes *libdwarf home directory/lib* and `${DYNINST_ROOT}/${PLATFORM}/lib` directories.

Once `make.config.local` is set you are ready to build Dyninst. Change to the `core` directory and execute the command `make DyninstAPI`. This will build Dyninst's mutator library, the Dyninst runtime library, and Dyninst's test suite. Successfully built binaries will be stored in a directory named after your platform at the same level as the `core` directory.

BUILDING ON WINDOWS

Dyninst for Windows is built with Microsoft Visual Studio 2003 project and solution files. Building Dyninst for Windows is similar to UNIX in that it is a four step process: Unpack the DyninstAPI source code, install Dyninst's package dependencies, configure Visual Studio to use the dependencies, and run the build system.

Dyninst source code is distributed as part of a `tar.gz` package. Most popular unzipping programs are capable of handling this format. Extracting the Dyninst tarball results in two directories: `core` and `scripts`.

Dyninst for Windows depends on Microsoft's Debugging Tools for Windows, which could be found at <http://www.microsoft.com/whdc/devtools/debugging/default.mspx> at the time of this writing. Download these tools and install them at an appropriate location. Make sure to do a custom install and install the SDK, which is not always installed by default. For the rest of this section, we will assume that the Debugging Tools are installed at `c:\program files\Debugging Tools for Windows`. If this is not the case, then adjust the following instruction appropriately.

Once the Debugging Tools are installed, Visual Studio must be configured to use them. We need to add the Debugging Tools include and library directories to Visual Studios search paths. In Visual Studio 2003 select `Options...` from the `tools` menu. Next select `Projects` and

VC++ Directories from the pane on the left. You should see a list of directories that are sorted into categories such as ‘Executable files’, ‘Include files’, etc. The current category can be changed with a drop down box in the upper right hand side of the Dialog.

First, change to the ‘Library files’ category, and add an entry that points to `C:\Program Files\Debugging Tools for Windows\sdk\lib\i386`. Make sure that this entry is above Visual Studio’s default search paths.

Next, Change to the ‘Include files’ category and make a new entry in the list that points to `C:\Program Files\Debugging Tools for Windows\sdk\inc`. Also make sure that this entry is above Visual Studio’s default search paths. Some users have had a problem where Visual Studio cannot find the `cvconst.h` file. You may need to add the directory containing this file to the include search path. We have seen it installed at `$(VCInstallDir)\..\Visual Studio SDKs/DIA SDK/include`, although you may need to search for it.

Once you have installed and configured the Debugging Tools for Windows you are ready to build Dyninst. First, you need to create the directories where Dyninst will install its completed build. From the `core` directory you need to create the directories `../i386-unknown-nt4.0/bin` and `../i386-unknown-nt4.0/lib`. Next open the solution file `core/DyninstAPI.sln` with Visual Studio. You can then build Dyninst by select ‘Build Solution’ from the build menu. This will build the Dyninst mutator library, the runtime library, and the test suite.

APPENDIX D – DYNINST PERFORMANCE

This appendix describes how to tune Dyninst for optimum performance. During the course of a run, Dyninst will perform several types of analysis on the binary, make safety assumptions about instrumentation that is inserted, and rewrite the binary (perhaps several times). Given some guidance from the user, Dyninst can make assumptions about what work it needs to do and can deliver significant performance improvements.

There are two areas of Dyninst performance users typically care about. First, the time it takes Dyninst to parse and instrument a program. This is typically the time it takes Dyninst to startup and analyze a program, and the time it takes to modify the program when putting in instrumentation. Second, many users care about the time instrumentation takes in the modified mutatee. This time is highly dependent on both the amount and type of instrumentation put it, but it is still possible to eliminate some of the Dyninst overhead around the instrumentation.

The following subsections describe techniques for improving the performance of these two areas.

APPENDIX D.1 – Optimizing mutator performance

Time in the Dyninst mutator is usually taken up by either parsing or instrumenting binaries. When a new binary is loaded Dyninst will analyze the code, looking for instrumentation points, global variables, and attempting to identify functions in areas of code that may not have symbols. Upon user request, Dyninst will also parse debug information from the binary, which includes local variable, line, and type information.

All of these items are parsed lazily, that is Dyninst won't try to generate this information until it is asked for. Information is parsed on a per-library basis, so a request for information about a specific library function will cause Dyninst to parse information about all functions in that library. Much of the Dyninst parsing performance problems can be removed, or mitigated, by structuring the mutator application so that it only requests information from Dyninst if and when it needs it.

Not all operations require Dyninst to trigger parsing. Some common operations that lead to parsing are:

- Requesting a `BPatch_instPoint` object
- Any operation on a `BPatch_function` other than getting its name

Debugging information is lazily parsed separately from the rest of the binary parsing. Accessing line, type, or local variable information will cause Dyninst to parse the debug information for all three of these.

Another common source of mutator time is spent re-writing the mutatee to add instrumentation. When instrumentation is inserted into a function, Dyninst may need to rewrite some or all of the function to fit the instrumentation in. If multiple pieces of instrumentation are being inserted into a function, Dyninst may need to re-write that function multiple times.

If the user knows that they will be inserting multiple pieces of instrumentation into one function, they can batch the instrumentation into one bundle, so that the function will only be re-written once, using the `BPatch_process::beginInsertionSet` and `BPatch_process::endInsertionSet` functions (see section 4.2). Using these functions can result in a significant performance win when inserting instrumentation in many locations.

To use the insertion set functions, add a call to `beginInsertionSet` before inserting instrumentation. Dyninst will start buffering up all instrumentation insertions. After the last piece of instrumentation is inserted, call `endInsertionSet`, and all instrumentation will be atomically inserted into the mutatee, with each function being rewritten at most once.

APPENDIX D.2 – Optimizing Mutatee Performance

As instrumentation is inserted into a mutatee it will start to run slower. The slowdown is heavily influenced by three factors: the number of points being instrumentated, the instrumentation itself, and the Dyninst overhead around each piece of instrumentation. The Dyninst overhead comes from pieces of protection code (described in more detail below) that do things such as sav-

ing/restoring registers around instrumentation, checking for instrumentation recursion, or performing thread safety checks.

The factor by which Dyninst overhead influences mutatee run-time is dependant on the type of instrumentation being inserted. When inserting instrumentation that runs a memory cache simulator, the Dyninst overhead may be negligible. On the other-hand, when inserting instrumentation that increments a counter the Dyninst overhead will dominate the time spent in instrumentation. Remember, optimizing the instrumentation being inserted may sometimes be more important than optimizing the Dyninst overhead. Many users have had success writing tools that make use of Dyninst's ability to dynamically remove instrumentation as a performance improvement.

The instrumentation overhead results from safety and correctness checks inserted by Dyninst around instrumentation. Dyninst will automatically attempt to remove as much of this overhead as possible, however it sometimes must make a conservative decision to leave the overhead in. Given additional, user-provided information Dyninst can make better choices about what safety checks to leave in. An unoptimized post-Dyninst 5.0 instrumentation snippet looks like the following:

Save General Purpose Registers	In order to ensure that instrumentation doesn't corrupt the program, Dyninst saves all general purpose registers.
Save Floating Point Registers	Dyninst may decide to seperatly save any floating point registers that may be corrupted by instrumentation.
Generate A Stack Frame	Dyninst builds a stack frame for instrumentation to run under, this provides the illusion to instrumentation that it is running as its own function.
Calculate Thread Index	Calculate an index value that identifies the current thread. This is primarily used as input to the Trampoline Guard.
Test and Set Trampoline Guard	Test to see if we are already recursively executing under instrumentation, and skip the user instrumentation if we are.
Execute User Instrumentation	Execute any <code>BPatch_snippet</code> code.
Unset Trampoline Guard	Marks the this thread as no longer being in instrumentation
Clean Stack Frame	Clean the stack frame that was generated for instrumentation.
Restore Floating Point Registers	Restore the floating point registers to their original state.
Restore General Purpose Registers	Restore the general purpose registers to their original state.

Dyninst will attempt to eliminate as much of its overhead as is possible. The Dyninst user can assist Dyninst by doing the following:

- **Write `BPatch_snippet` code that avoids making function calls.** Dyninst will attempt to perform analysis on the user written instrumentation to determine which general purpose and floating point registers can be saved. It is difficult to analyze function calls that may be nested arbitrarily deep. Dyninst will not analyze any deeper than two levels of function calls before assuming that the instrumentation clobbers all registers and it needs to save everything.

In addition, not making function calls from instrumentation allows Dyninst to eliminate its tramp guard and thread index calculation. Instrumentation that does not make a function call cannot recursively execute more instrumentation.

- **Call `BPatch::setTrampRecursive(true)` if instrumentation cannot execute recursively.** If instrumentation must make a function call, but will not execute recursively, then enable trampoline recursion. This will cause Dyninst to stop generating a trampoline guard and thread index calculation on all future pieces of instrumentation. An example of instrumentation recursion would be instrumenting a call to `write` with instrumentation that calls `printf`—`write` will start calling `printf` `printf` will re-call `write`.
- **Call `BPatch::setSaveFPR(false)` if instrumentation will not clobber floating point registers.** This will cause Dyninst to stop saving floating point registers, which can be a significant win on some platforms.
- **Use simple `BPatch_snippet` objects when possible.** Dyninst will attempt to recognize, and peep-hole optimize, simple, frequently used code snippets when it finds them. For example, on x86 based platforms Dyninst will recognize snippets that do operations like `'var = constant'` or `'var++'` and turn these into optimized assembly instructions that take advantage of CISC machine instructions.

~

~BPatch_thread · 23

A

attachProcess · 7, 10

B

BPatch_addrSpec_NP · 53
 BPatch_arithExpr · 35
 BPatch_basicBlockLoop · 47
 BPatch_boolExpr · 36
 BPatch_breakPointExpr · 36
 BPatch_bytesAccessedExpr · 36, 62
 BPatch_cblock · 49
 BPatch_constExpr · 37
 BPatch_countSpec_NP · 53
 BPatch_effectiveAddressesExpr · 37
 BPatch_flowGraph · 42
 BPatch_funcCallExpr · 37
 BPatch_function · 24
 · 38
 BPatch_ifExpr · 38
 BPatch_image · 29
 BPatch_memoryAccess · 52
 BPatch_module · 32
 Bpatch_nullExpr · 39
 BPatch_opCode · 26
 Bpatch_paramExpr · 38
 · 39
 BPatch_point · 27
 BPatch_retExpr · 39
 BPatch_sequence · 39
 BPatch_Set · 50
 BPatch_snippet · 35
 BPatch_sourceBlock · 49
 BPatch_sourceObj · 23
 BPatch_tidExpr · 39
 BPatch_type · 40
 BPatch_variableExpr · 41
 BPatch_Vector · 50
 BPatchErrorCallback · 11, 13
 BPatchErrorLevel · 11, 13, 19, 23
 BPatchPostForkCallback · 12
 BPatchThreadEventCallback · 11, 13

C

Class BPatch_basicBlock · 44, 45

dyninstAPI

continueExecution · 15, 22
 createArray · 6
 createEnum · 6
 createInstPointAtAddr · 29
 createPointer · 7
 createProcess · 7, 10
 createScalar · 6
 · 43
 createStruct · 6
 createTypedef · 6
 createUnion · 7

D

deleteSnippet · 17, 23
 detach · 19, 20, 23
 dominates · 46
 dumpCore · 15, 22, 23
 dumpImage · 15, 22
 · 15, 22

E

· 15, 22

F

· 43
 findFunction · 30, 32, 33, 50
 · 31
 findPoint · 26
 findType · 31
 findVariable · 31
 free · 16, 22
 funcJumpExpr · 37

G

getAddress · 28
 · 46
 getAllBasicBlocks · 42
 getAllDominates · 46
 getBaseAddr · 27, 41
 getBlockNumber · 46
 getByteCount_NP · 53
 getCalledFunction · 28
 getCallStack · 20, 21
 getCblocks · 40
 getCFG · 27
 getComponents · 40, 42, 49
 getConstituentType · 40
 getContainedLoops · 47, 48

getCost · 35
 getCurrentSnippets · 28
 getDataClass · 40
 · 28
 · 7
 getEntryBasicBlock · 42
 getExitBasicBlock · 42
 getFP · 50
 getFrameType · 50
 getFunctions · 49
 getHigh · 41
 getImage · 14, 20, 22, 23, 31, 33, 34
 getImm · 53
 getImmediateDominates · 46
 getImmediateDominators · 46
 getInheritedVariable · 16, 22
 getLanguage · 24
 getLineAndFile · 22, 27
 getLineToAddr · 27, 32, 35
 getLoopBasicBlocks · 48
 getLoopHead · 48
 getLoops · 42, 43
 getLow · 41
 getMangledName · 24, 25
 getMemoryAccess · 28
 getModule · 26
 getModuleName · 26
 getModules · 29
 getName · 24, 34, 41
 getObjParent · 24
 getParams · 25
 getPC · 50
 getPointType · 27
 getProcedures · 29, 34
 getReg · 53
 getReturnType · 25
 getSize · 27
 getSourceBlock · 46
 getSourceFile · 49
 getSourceLines · 49
 getSourceObj · 24
 getSources · 43, 45
 getSrcType · 24
 getStartAddr_NP · 53
 getTargets · 46
 getThreads · 7, 10
 getType · 35
 getUniqueString · 31, 34

I

insertSnippet · 16, 23
 isALoad_NP · 52
 isAPrefetch_NP · 52
 isAStore_NP · 52
 isCompatible · 41
 isInstrumentable · 25
 · 25, 34
 isSharedLib · 25, 34

dyninstAPI

isStopped · 15, 22
 isTerminated · 15, 22

L

libraryName · 25, 34

M

malloc · 15, 22
 Memory Access Classes · 52
 Memory Access Snippets · 62

O

oneTimeCode · 16, 20, 21, 22

P

pollForStatusChange · 8, 9
 prefetchType_NP · 53
 · 50

R

readValue · 41
 registerDynamicLinkCallback · 13, 14
 registerErrorCallback · 11
 registerExecCallback · 12
 registerExitCallback · 13
 registerPostForkCallback · 12
 registerPreForkCallback · 12
 removeFunctionCall · 17, 23
 replaceFunction · 18, 23
 replaceFunctionCall · 18, 23

S

setDebugParsing · 8
 setInheritSnippets · 18, 19, 23
 setMutationsActive · 19, 23
 setTrampRecursive · 8
 setTypeChecking · 8
 · 50
 stopExecution · 15, 22
 stopSignal · 15, 22

T

terminateExecution · 15, 22
 Type Checking · 54

U

usesTrap_NP · 28

W

writeValue · 41

REFERENCES

1. B. Buck and J. K. Hollingsworth, "An API for Runtime Code Patching," *Journal of Supercomputing Applications (to appear)*, 2000.
2. J. K. Hollingsworth and B. P. Miller, "Using Cost to Control Instrumentation Overhead," *Theoretical Computer Science*, **196**(1-2), 1998, pp. 241-258.
3. J. K. Hollingsworth, B. P. Miller, and J. Cargille, "Dynamic Program Instrumentation for Scalable Performance Tools," *1994 Scalable High-Performance Computing Conf.*, Knoxville, Tenn., pp. 841-850.
4. J. K. Hollingsworth, B. P. Miller, M. J. R. Goncalves, O. Naim, Z. Xu, and L. Zheng, "MDL: A Language and Compiler for Dynamic Program Instrumentation," *International Conference on Parallel Architectures and Compilation Techniques (PACT)*. Nov. 1997, San Francisco, pp. 201-212.
5. J. R. Larus and E. Schnarr, "EEL: Machine-Independent Executable Editing," *PLDI*. June 18-21, 1995, La Jolla, CA, ACM, pp. 291-300.